USER GUIDE



GeoDMS GUI

VERSION 7.180



User Guide GeoDMS GUI 7.180

Author: Martin van der Beek & Jip Claassens, Object Vision BV

Amsterdam, September 2018

Copyright © Object Vision BV

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.1, published by the Free Software Foundation; with the Front-Cover Texts being User Guide GeoDMS GUI 7.180. A copy of the license is included in the section entitled "GNU Free Documentation License" (http://www.gnu.org/licenses/fdl.html).



Table of Contents

TABLE OF CONTENTS	3
PART I GENERAL STRUCTURE	5
CHAPTER 1: INTRODUCTION	5
1.1 MAIN COMPONENTS OF A GEODMS PROJECT	5 5 6 6
CHAPTER 2 DESKTOP COMPONENTS	7
2.1 MAIN COMPONENTS OF THE APPLICATION	7
CHAPTER 3: TREEVIEW1	10
3.1 INTRODUCTION 1 3.2 ICONS USED IN THE TREEVIEW 1	10 10
CHAPTER 4: MAIN AND POP-UP MENU OPTIONS1	12
4.1 INTRODUCTION 1 4.2 MENU OPTIONS 1 4.2.1 File Menu 1 4.2.2 Edit Menu (only in Administrator mode) 1 4.2.3 View Menu 1 4.2.4 Insert Menu (only in Administrator mode) 1 4.2.5 Tools Menu 1 4.2.6 Windows Menu 1 4.2.7 Help Menu 2 4.2.7 Help Menu 2 5.1 GENERAL 2 5.2 EXPLORE 2 5.3 PROPERTIES 2 5.4 METADATA 2 5.5 STATISTICS 3 5.6 VALUE INFO 3 5.7 CONFIGURATION 3 5.8 XML 3 5.9 SOURCE DESCRIPTION 3	12 12 12 12 14 15 16 17 22 24 24 25 26 28 31 32 33 34
CHAPTER 6: INTRODUCTION	35
6.1 DATA VISUALIZATION	35
CHAPTER 7: MAP VIEW 3 7.1 INTRODUCTION 3 7.2 LAYER TYPES 3	37 37 38
7.3 ACTIVE LAYER	39 39 14 45



CHAPTER 8: TABLE	
8.1 ACTIVATING A TABLE	
8.2 TABLE	
8.3 TOOLS	
CHAPTER 9: HISTOGRAM VIEW	
9.1 HISTOGRAM VIEW	
CHADTED 10, INCEDT CLASSIFICATION AND DALETTE	52
Chapter 10: INSERT CLASSIFICATION AND PALETTE	
10.1 CLASSIFICATIONS AND PALETTES	
IU.2 INSERT CLASSIFICATION AND PALETTE DIALOG	54
PART III COMPOSERS	
INTRODUCTION:	57
CHADTED 11. INSERT CONTAINED	57
11.1 CONTAINERS	
CHAPTER 12: INSERT DATA ITEM	
CHAPTER 13: INSERT ENTITY/UNIT	
13.1 VALUES AND DOMAIN UNITS	59
13.2 INSERT ENTITY/UNIT DIALOGUE	59
13.3 TABLE UNIT	
13.5.1 Treettem selection alalogue	
13.5 OUANTITY UNIT	
13.6 POINT UNIT	66
13.7 Shape unit	67
13.8 CODE UNIT	
13.9 STRING UNIT	
13.10 BOOLEAN UNIT	
CHAPTER 14: EXPRESSION DIALOGUE	
14.1 EXPRESSIONS	
14.2 EXPRESSION DIALOGUE	
15.1 INTRODUCTION	
15.2 LINKING PRIMARY DATA	
15.2.2 dBase (versions III, IV or V):	
15.2.3 ODBC source	77
15.2.4 Shapefile	
15.3 EXPORTING PRIMARY DATA	
15.3.2 Bitmap/Tiff	
15.3.3 ASCII attribute	



PART I GENERAL STRUCTURE

Chapter 1: Introduction

1.1 Main components of a GeoDMS project

A GeoDMS project contains the following components:

- The GeoDMS Engine (Geographic Data and Model Server), a generic set of DLL's that control, retrieve, store and calculate the primary data and model results
- The GeoDMS GUI, a generic client application that visualizes the primary data, the model results and the calculation logic with a set of primary data viewers. Furthermore, it supports the user in extending/editing the model logic, importing and exporting new primary data and savings all these 'settings' in a new configuration.
- The (default) configuration. A hierarchical set of configuration files that describe the primary data, the model logic, and the way to visualize both. For this User Guide, the Landuse Scanner demo configuration is used.
- A set of primary data files that are configured in the configuration.

This user guide mainly focuses on the GeoDMS GUI. How to set up a configuration is described in the modeler's guide. Both guides can be found on the website of Object Vision (<u>http://www.objectvision.nl/GeoDMS</u>). Information about the example data can be retrieved as metadata in the system (see paragraph 5.5, Detail Pages > Metadata).

The GeoDMS GUI is the user interface of the system. As mentioned above the purpose of the application is to:

- View all the primary data and model results. A hierarchical structure is used in the configuration to find the requested information (data element). This hierarchical structure of so-called tree items is presented in a Treeview. With a set of viewers, the primary data, as well as the model logic, can be visualized.
- Adapt or extend the model logic or the way to visualize data by initiating new cases, create new or edit existing expressions and classifications. Also, data can be exported in different data formats.
- Store and retrieve the settings of the visualization of the primary data or model results in a desktop or the complete configurations with all calculation rules in/from a new configuration.

The GeoDMS GUI is a Windows-based application. This user guide does not describe the generic Windows functionality like how to close, maximize or minimize a window. For more information on these topics refer to your Windows user guide. An Internet connection and installed browser are preferred, as the most actual help can be found at the above-mentioned website.

1.2 How to read this guide

This guide focuses mainly on the end-user, who views the primary data, calculates model results, initiates new cases and makes limited extensions and editions to the configuration. A detailed description of the structure of the client application, the different viewers and the composers are, therefore, described. This user guide does not contain sufficient information for modelers to set up a new configuration or a new



calculation scheme. For this purpose, we refer to the modeler's guide, describing the basics on how to configure a model with the GeoDMS.

This user guide is split into two parts. Part 1 describes the generic structure of the application, the menu options and the three main panels in the desktop (the Treeview, the Detail Pages and the Eventlog). Part 2 focuses on the data viewers that can be used to visualize primary data, model results and calculation/model logic.

1.3 *System requirements*

See for the latest information on the system requirements the Object Vision website.

1.4 Installation Instructions

See for the latest installation instruction the Object Vision website.



Chapter 2 Desktop components

2.1 Main components of the application

After activating the application, the following window is presented:

GeoDMS GUI - demo.dms in C:\GeoDMS\	ProjDir\lus_demo\cfg	– 🗆 X
<u>File View Tools Window H</u> elp		
Comment_Stuation Generative Stuation Generative Stuation Simulations	s in C:\GeoDMS\ProjDir\lus_demo\cfg	Image: Supple in the second state of the second state o
©@@@@@ Logging started for C:/GeoDMS/L Read_fss(C:/GeoDMS/LocalData/lus_demo/C	.ocalData/lus_demo/trace.log at 09/17/18 - 17:02:43 CalCachay64 v7 180 Cachainfa)	
init ok	accachekotky (100,cdCHEIIIO)	
	3 active DataItems - max processing time: 00:00:00	Desktop: <default desktop=""></default>

Figure 2.1: Main window of the GeoDMS GUI

In this main window the following components can be distinguished:

GeoDMS GUI - demo.dms in D:\GeoDMS\prj\lus_demo\cfg

Figure 2.2: Title bar with the product name and opened configuration

File View Tools Window Help

Figure 2.3: Menu bar with main menu options

Figure 2.4: An editable item path that can be used to jump to other items (use F5 or mouseclick to search)

Figure 2.5: Toolbar with view-specific tools

X





Figure 2.6: Treeview with root item expanded.



Figure 2.7: View area in which data viewers can be activated.

```
        I active DataItem - max processing time: 00:00:00
        Desktop: <Default Desktop>

        Figure 2.8: Status bar presenting hints and status information.
        Desktop: <Default Desktop>
```

These components, except for the Treeview and Toolbar, are always visible. The Treeview can be closed (and re-opened) with the menu option View>Tree, or with the ALT-0 keyboard combination, the toolbar with the ALT-3 keyboard combination.

Two more components are always positioned at a fixed location. The Detail Pages, to be opened and closed with the menu option View>Detail Pages, or with the ALT-1 keyboard combination, are always positioned at the right side of the main window. The following figure shows an example of the Detail Pages for the root item:

← → Back Forward <u>⊡</u> <u>G</u> eneral Σ=∩ Value Info	왕 한 Stop Befresh Q Explore 딸 Pr [딸 Configuratio	roperties 🔇 Met in 😭 XML	adata ∑=n <u>S</u> tatistics Source <u>D</u> escr
demo FullName ProgressState <u>CalculationRule</u> CacheEntry	MetaInfoReady at 1 <none> "</none>		*

Figure 2.9: Detail Pages opened for the root tree item

The Detail Pages are a set of tabs that present information on the selected Treeview item. These pages will be described in detail in chapter 5.



The third component that is always opened at the bottom of the main window is the Eventlog view. This view can be opened and closed with the menu option View> Eventlog, or with the ALT-2 keyboard combination. The view shows the events that are executed by the application, as presented in the following example:

TConfiguration.L created config	oadConfiguration: stam.dm	S
init ok		

Figure 2.10: Eventlog view with start-up events of the GeoDMS GUI

This Eventlog is mainly interesting for experienced users to analyze which actions are executed. The messages occurring in this log will not be described in this guide.

The three mentioned components (Treeview, Detail Pages and Eventlog) have a fixed position. The size of these components can be adapted with a minimum and maximum size. The appearance of these components, the width of the Treeview and the Detail Pages and the height of the Eventlog is stored in the user-specific configuration settings of the registry. This means the next time the application is opened, the size of the components will be maintained.



Chapter 3: Treeview

3.1 Introduction

The Treeview is the main navigation component of the application. It presents the hierarchical structure of a configuration in a view like the Windows Explorer. By default, the root and the first level items are shown (the root item is expanded). Each item in the tree (called a tree item) is presented with a name and an icon. The main function of the icons is to show the default viewer for each tree item. In paragraph 3.2 these icons are explained.

The selected item in the Treeview is the active item in the application. This is an important concept, as many functions of the application work on the active tree item. By clicking the right mouse button a pop-up menu can be activated, with a set of menu options that work on this active tree item. This also applies to most main menu options and to the Detail Pages. The pop-up menu options and most main menu options are described in chapter four. The Detail Pages are described in chapter five.

3.2 Icons used in the Treeview

The main purpose of the icons is to show which default viewer is used for an item. Double-clicking or pressing the Enter key on a selected tree item activates this viewer. The following icons are used to indicate this default viewer:

2	A data item that can be viewed on a map. This implies the domain of the data
	item has a geographic relation (see modeler's guide for how to configure a
	geographic domain unit). Dependent on the geographic domain, the data is
	visualized in a grid, point, arc or polygon layer.
	A data item that cannot be visualized on a map (it has no geographic relation)
	but can be viewed in a Table.

The following two icons do not indicate the default viewer but indicate data items with a specific function (classifications and palettes, see chapter 10).

tt	A data item that contains a classification (a set of classes). A classification can
	be made or edited with the classification and palette composer, see chapter 10
3	A data item that contains a palette (a set of color values that correspond to a
	classification). A palette can be edited with the palette composer, see chapter
	10

Not all tree items are data items. For the non-data items (these items cannot be viewed with a primary data viewer), the following icons are in use:

	A tree item with no data items and subitems that also have no data items. The
	icon is used for containers grouping other containers or units.
1	A tree item with no data item, but with data items as subitems. All subitems of
	this item with the same domain unit can be viewed in a Table.
	A tree item with no data item and no subitems, e.g. a unit



Tree items can have a different status and have corresponding text colors, three status types are distinguished:

- 1. *Valid (blue)*: the results are calculated and the integrity checks configured for the item and its suppliers are met.
- 2. *Not Calculated (pink)*: the items are not checked and not calculated.
- 3. *Failed (red)*: the application failed in updating the results or the integrity checks are not met. In the first case, the results are not available; an error is raised indicating what problem occurred while updating the tree item. In the second case, the results are available and can be presented in a view; a warning color indicates the results are not valid.

The application controls when and how to update tree items. If a user requests a view on a data item, the required tree items are first updated, before the results are presented in the view. If a tree item has become valid, this status is 'stored' until changes are made in the calculation rules. This means the second time the same view (or another view requiring the same data items) is requested, the data item is already valid and the results can be visualized immediately.



Chapter 4: Main and pop-up menu options

4.1 Introduction

The main and pop-up menu options are related. With the pop-up menu options, the user can activate functions on the selected tree item. The related main menu options also function on the selected tree item. The main menu additionally contains a set of generic functions like saving a configuration or tiling the viewer windows. In this chapter, the main menu options are described. If the option can also be activated from the pop-up menu option this is indicated by (P). Some options can only be activated from the pop-up menu, this is also indicated.

4.2 Menu options

4.2.1 <u>F</u>ile Menu

File	Edit	View	Insert	Tools	Window	Н	lelp			
	Open	Configu	uration F	ile						Ctrl+O
	Save C	Save Configuration As Ctrl+S								
	Reope	n curre	nt config	guration						Alt+R
	New D	esktop.								
	Open l	Desktop	o							
	Set Sta	rtup De	esktop							
	Save D	esktop	to File							
	Export	Primar	y Data							۱.
	Export	Export Viewports								
	1 c:\da	ata\dev	\web\dr	ns\dowr	nloads\lus\l	lus_	_500m\cf	ig\demo	.dms	
	2 p:\za	a\cfg\z	aa.dms							
	3 p:\w	kn\cfg\	∖stam.dr	ns						
	4 p:\za	a∖cfg_ł	hoogtek	aart\zaa.	dms					
	5 p:\n\	wg\cfg\	\nwg.dn	ns						
	6 p:\sc	h_2010	\cfg\sch	n.dms						
	7 c:∖da	ata\dev	\prj\hon	∖cfg_old	l\default.dr	ms				
	8 c:\da	ata\dev	\prj\hon	_nc\cfg	\default.dm	ns				
	9 c:\tm	np\zaa.	dms							
	Exit									

Figure 4.1: File menu

Open Configuration File: Open a Windows file dialogue to select a new configuration. The current configuration is closed with a question whether the changes must be saved.



Save Configuration As: Open a Window file dialogue to specify a new root configuration file (or select an existing root configuration file that will be overwritten). In subdirectories, the whole configuration will be saved. If a configuration is saved to a file that is read-only, or if its configuration files in a subfolder are read-only, an error is raised.

Reopen current configuration: Reopens the current configuration with the current and active expanded item and desktop. If a configuration is edited, this way the configuration can easily be reopened in the same state.

<u>New Desktop</u>: Create a new desktop, based on a desktop template. A desktop is defined as the set of opened map and data viewers, including the specification of the:

- set of layers and their order in each map view with the properties
 - visible
 - for thematic layers, the used classification
- The area of interest in each map view
- The set of columns, column widths and sort order in each Table

After activating this option, a dialogue is presented in which a desktop template can be chosen. This offers the possibility of making a new desktop, based on an existing desktop functioning as a template. If no desktop templates are available, only the empty desktop option can be activated to make a new desktop. In the next dialogue, a name must be specified for the desktop. The active desktop name is presented in

the status bar of the application: Desktop: <Default Desktop>

Open Desktop: Open a dialogue to select a desktop from the available desktops in the current configuration. The selected desktop is opened.

Set Startup Desktop: Open a dialogue to select a desktop in the current configuration that is used as start-up desktop each time the current configuration is opened.

Save Desktop to file: Saves the desktops in the active configuration to a separate configuration file.

Export Primary Data (P): Export primary data to a bitmap, .dbf (or Shapefile), ASCII grid or .csv file. The option is only active for the relevant data items. Select the menu option and choose from the submenu the requested data format. If configured, exports of primary data can be accompanied by a .ini or .xml file, containing meta information on this primary file. See paragraph <u>9.3.1 of the modeler's guide</u> for more information on how to configure metadata files.

Export Viewports: Exports the set of opened viewports to bitmaps. A viewport is the part of the map view, in which the actual geographic data is shown. The export settings (including export directory and file names) are configured in the ExportSettings configuration. Activating this option results in a new dialogue, in which all active viewports are shown and selected. From this list, you can also select a subset of the viewports to be exported. Information about the number of pixels/bitmaps per viewport is also presented.

Recent configurations: The recently opened configurations are presented, to easily select one of these configurations. The number of configurations is limited to nine.



Exit: Exit the application.

4.2.2 Edit Menu (only in Administrator mode)

Edit	View Insert Tools V	Vindow Help
	Config Source	Ctrl+E
	Definition	Ctrl+Alt+E
	Classification and Palette	Ctrl+Alt+C
	Update Treeitem	Ctrl+U
	Update Subtree	Ctrl+T
	Invalidate TreeItem	Ctrl+I
	Copy TreeItem	Ctrl+C
	Paste Treeltem	Ctrl+V
	Delete TreeItem	Ctrl+Del
	Edit Label ActiveWindow	

Figure 4.2: Edit menu

Config Source (P): Edit the config source of an item with the DMS editor (Notepad ++ or Crimson Editor is advised, see <u>here</u>). The editor needs to be specified in the Tools > Options > General Settings > DMS editor option (see 4.2.5). The DMS editor is activated with the relevant dms file and if supported by the editor, the correct line and position. After editing and saving, use the File > Reopen current configuration open to open the configuration in the same state (expanded and active item and desktop).

Definition (P): Activate

- The Edit Classification and Palette dialogue if the selected data item is a classification class's item. See chapter 10 for more information on classifications and palettes.
- The Edit Palette dialogue if the selected data item is a color palette.
- The Expression dialogue for all other items. This dialogue is used to set or edit the expression of a tree item. See chapter 16 for more information on the Expression dialogue.

Classification and Palette (P): Activate the Edit Classification and Palette dialogue for all data items for which a classification and palette is configured. This classification and palette can be configured for the data item itself or for its values unit. See chapter 10 for more information on classifications and palettes.

<u>Update TreeItem (P)</u>: Update a data item with the status invalidated. The option is only enabled for invalidated data items. The result of the action can be a valid data item (update succeeded) or a failed data item (update raised an error).

Update Subtree (P): Update the subitems of a tree item. The option is only enabled for tree items with invalidated subitems. The result of the action can be a valid set of subitems (update succeeded) or one or more failed items (update raised an error).



Invalidate TreeItem (P): Explicitly invalidate an item to ensure it will be recalculated when the results are requested in a view.

Copy TreeItem (P): Copy a tree item to the Windows clipboard, to paste the item into another container.

Paste TreeItem (P): Paste a copied tree item with the same name. An item needs to be copied first before the paste option becomes enabled. As two tree items with the same name are not allowed in the same container, a copied item cannot be pasted in the same container (the option is disabled). Be aware: Pasting items in a new container can cause invalid tree items (e.g. because the container of the copied item a using or storage property was configured, which is not a property of the copied item and, therefore, not copied to the new item). Primary data is not copied; therefore, the copy/paste functionality cannot be used to make a copy of a classification. Use the save as function in the edit classification and palette dialogue for this purpose.

Delete TreeItem (P): Delete a tree item with all its subitems. If a tree item cannot be deleted, because it is referred to by other tree items, (e.g. in an expression), a message is presented indicating the item could not be deleted. First, delete the referring tree item before the referred tree item can be deleted. Still deleting tree items can cause some incorrect working functionality. Be cautious with deleting tree items, especially with items referred to from multiple places.

Edit Label ActiveWindow: The Active View (see part II of this reference for information on viewers) can be provided with a label, indicating the contents of this view. The menu option becomes active if a view is opened. In a text box, a view label can be given. The view label is presented in the title bar of the view.

View	Insert Tools	Window He	elp	
	<u>D</u> efault	Enter		
	<u>M</u> ap	Ctrl+M		
	Ta <u>b</u> le	Ctrl+D		
	<u>H</u> istogram	Ctrl+H		
	Process Schemes		Þ	
	Treeview	Alt+0		
	Det <u>a</u> il Pages	Alt+1		
	E <u>v</u> entlog	Alt+2		
✓	T <u>o</u> olbar	Alt+3		

4.2.3 <u>V</u>iew Menu

Figure 4.3: View menu

Default (P): Activate the default viewer for the selected data item. This option is only enabled for data items. The default viewer for all data that can be visualized in a map is the map view. For all other data items, the default viewer is the Table view.

Map (P): Activate the map view for the selected data item. In a submenu, the layer type must be chosen (in this version only default is implemented). See chapter 7 for



more information on the map view and the layer types. The map view option becomes enabled if the selected data item can be visualized in a map view.

Table (P): Activate the Table for the selected data item. See chapter 8 for more information on the Table. The Table option becomes enabled if the tree item can be visualized in a Table.

<u>H</u>istogram (P): Activate the histogram for the selected data item. See chapter 9 for more information on the histogram. The histogram option becomes enabled if the tree item can be visualized in a histogram.

Process Schemes (P) (only in Administrator mode): Activate the process scheme for the selected tree item. In the submenu, the process scheme type must be selected.

Treeview: Show or hide the Treeview at the left side of the main window. See chapter 3 for more information on the Treeview.

Detail pages: Show or hide the Detail Pages at the right side of the main window. See chapter 5 for more information on the Treeview.

Event log: Show or hide the Eventlog window at the bottom side of the main window.

Toolbar: Show or hide the toolbar at the top side of the main window.

4.2.4 Insert Menu (only in Administrator mode)



Figure 4.4: Insert menu

The first four menu options insert items or sets of items at the location of the selected tree item:

Container (P): Insert a new container as a subitem of the selected tree item. The Insert container dialogue is activated. See chapter 12 for more information on containers and this dialogue.

Data Item (P): Insert a new data item as a subitem of the selected tree item. The insert data item dialogue is activated. See chapter 13 for more information on this dialogue.

<u>Entity</u>/Unit (P): Insert a new entity or unit as a subitem of the selected tree item. The Insert Entity/Unit dialogue is activated.



External Data Link (P): Insert a link to an external data source, this is implemented for ASCII grids, dBase files, ODBC sources and Shapefiles. They will be configured as subitem(s) of the selected tree item.

The two options below the line insert sets of items at a pre-defined, configured location in the tree. This location is configured in the config.ini file accompanying each configuration. The location is independent of the selection of the active tree item.

Template Instantiation (P): Insert a new instantiation of a template. A dialogue is presented to specify the parameters for this instant ion.

Classification and Palette (P): Insert a new classification and palette in the classification container. The Insert Classification and Palette dialogue is activated. See chapter 10 for more information on classifications, palettes and this dialogue.

4.2.5 Tools Menu

File	View	Tools	Window	Help
		C)ptions	Ctrl+Alt+O

Figure 4.5: Tools menu

Options: activate the following dialogue to set some general properties:

– Object Visi	on	
😌 Options		×
General setting	S Current configuration ConfigSettings	
Help		
<u>U</u> rl:	http://www.objectvision.nl/geodms	
<u>H</u> elpfile:	http://www.objectvision.nl/geodms	
External prog	grams %ProgramFiles32%\Crimson Editor\cedt.exe /L:%L "%F"	<u> </u>
User modes		
Administrat	tor mode Show State Colors in TreeView	
TraceLogFil	le 🔽 Suspend View Updates to favour GUI	
✓ Parallel Proc	cessing <u>1</u> (tile based) 🔽 PP <u>2</u> (multiple calculation steps simultaneous	ly)
Paths		
LocalDataDir:	D:\LocalData	
<u>S</u> ourcelDataDir	r: D:\PBL\SourceData	
	<u>Ok</u> <u>A</u> pply <u>Cancel</u>	

Figure 4.6: General settings dialogue

The dialogue is split up into three tabs. The General settings tab is used to configure settings that apply to all configurations. These settings are stored in the user-specific registry setting. The Current configuration tab is used to configure settings that apply to the current configuration. These settings are stored in the configuration specific config.ini files. The ConfigSettings tab contains configuration specific setting that can be overruled for the local machine. These settings are stored in the registry.

In the General settings tab the following settings can be configured: **URL**: The URL that is used in the about box for more information on the data and model server

<u>Helpfile</u>: the URL that is used for online help on the data and model server.

It is not recommended to change the URL and Helpfile settings.

DMS editor: the path to an external text editor, including some parameters for how to position the cursor at a specific location in a configuration file. This functionality is used if errors occur in the configuration. If a text editor is configured, the GeoDMS GUI can open the configuration file and, if supported by the editor, indicate to the position in the file where the error was noticed. The following parameters can be set:



%F: file %L: line number in the file %C: column number in the file The exact syntax for the configuration depends on the used editor, see <u>here</u>.

<u>U</u>ser modes: The application can be configured in two modes:

- User mode. The administrator mode check box is not selected \Box .
- Administrator mode. The administrator mode checkbox is selected **▼**.

There are three differences between both modes:

- Hidden tree items. A tree item can be configured hidden by configuring the DialogType property to hidden. In the user mode, these items are not shown in the Treeview, the Detail Pages and the process schemes. In the administrator mode, all items are shown.
- The menu (and pop up menu) options Edit and Insert are only available in the administrator mode.
- Editing the properties. In the user mode, the dialogues are used to set properties for specific tasks. The properties in the detail page Properties (A) cannot be edited. In the administrator mode, some of these properties can be edited. *Be aware that editing properties in this dialogue can make the application unstable.*

If the Administrator mode is selected, the following options can be selected:

- 1. TraceLogFile. If this option is selected, a trace.log file is generated by the application. The trace.log file logs information about the calculation processes and can be used for debugging purposes. If the option is not selected, the file is not generated.
- 2. Show State Colors in Treeview. This option shows the state of an item (as described in & 3.2), visualized in different colors in the Treeview. The colors can be configured in the Current configuration tab. The color for valid items cannot yet be specified (default green).
- 3. Suspend View Updates to favor User Interaction. This option allows a user to interact with the system, even if the system is calculating results or updating views. The option can cause some errors and is therefore not supported in the user mode.
- 4. Parallel Processing 1(tile based) and PP2 (multiple calculation steps simultaneously). These options are implemented to support multi-threading (in development). It is advised to keep these options to the default settings for the GeoDMS version.

LocalDataDir:

The LocalDataDir is used as the base directory for (temporary) results like the CalcCache. See <u>http://www.objectvision.nl/geodms/directories-and-placeholders</u> for more information on directories and placeholders in the GeoDMS. The default setting for the LocalDataDir is C:\LocalData. This default setting can be overruled here.

SourceDataDir:

The SourceDataDir is used as the base directory for (large, read-only) sourcedata files, often used in multiple projects. See <u>http://www.objectvision.nl/geodms/directories-and-placeholders</u> for more information on directories and placeholders in the GeoDMS. The default setting for the SourceDataDir is C:\SourceData. This default setting can be overruled here.



Object Vision

The	Current	configuration	tah	nresents th	he follow	ing dialog	nie.
ne	Current	conniguration	ιαυ	presents tr	IE IOIIOW	iliy ulalou	jue.

Options	Х
General settings Current configuration ConfigSettings	
Map View Color settings	
No-data:	
Background	
TreeItem View Color settings	
<u>V</u> alid:	
NotCalculated:	
Failed:	
Default Classification Ramp Colors	
<u>S</u> tart	
End:	
Minimum size for DataItem specific swapfiles in CalcCache: 4000 byt	es
Threshold for Memory Flushing wait procedure 90 %	
<u>Ok</u> <u>Apply</u> <u>Cancel</u>	

figure 4.7: Current configuration dialogue

No-data color: Activate the button to select the no data color in the map views of the current configuration.

Background color: Activate the button to select the background color of the map views of the current configuration

TreeItem View Color Settings: Default these options are disabled. If in the General settings page the Administrator mode is selected, the option: Show State Colors in Treeview can be selected. The state of an item (as described in & 3.2) is then visualized in different colors in the Treeview. The colors for Valid, Invalidated or Failed items can be selected in this dialogue.

Default Classification Ramp Colors: In the classification and palette composer (see chapter 10), colors are default chosen for the first and the last class. These colors can be selected with this dialogue.

Minimum size for DataItem specific swap files in CalcCache: This setting is used to indicate the size of items that need to be saved in the CalcCache on disk. In general,



it is advised to keep this setting. See <u>http://www.objectvision.nl/geodms/calccache-guide</u> for more information.

Threshold for Memory Flushing wait procedure: a threshold value that indicates at which percentage of use of the internal memory the GeoDMS should start with flushing memory to keep the system responding. In general, it is advised to keep this setting.

The ConfigSettings tab presents a following dialog:

S Options	×
General settings Current configuration ConfigSettings	
CursusDataDir %sourceDataDir%/Cursus_voorjaar_2017	.ese
<u>Ok</u> <u>Apply</u>	cel

Figure 4.8: ConfigSettings dialog

The presented settings in this dialogue result from the items configured in the /ConfigSettings/Overridable container of a project configuration. The values in the blue boxes correspond to the values configured in the project configuration. The values in the dark green boxes are overruled for the local machine (and stored in the registry). With the Reset button, they can be reset to the configured values.



4.2.6 Windows Menu

Window Help	
<u>T</u> ile Horizontal	Ctrl+Alt+W
Tile <u>V</u> ertical	Ctrl+Alt+V
<u>C</u> ascade	Shift+Ctrl+W
Cl <u>o</u> se	Ctrl+W
C <u>l</u> ose All	Ctrl+L

Figure 4.9: Windows menu

<u>T</u>ile Horizontal: Tile the currently opened data viewers horizontally.

Tile <u>Vertical</u>: Tile the currently opened data viewers vertically.

<u>C</u>ascade: Cascade the currently opened data viewers.

Close all: Close all currently opened data viewers.

Windows: A list of all opened data views, the active view is indicated by a dot. A view can be activated from this list.

4.2.7 Help Menu



Figure 4.10: Help menu

Online Help: Open the Internet Browser installed on the local machine with the URL specified for the Help file in the Tools > Options dialogue.

About: Open the About box for information on the version and development team of the application

Index: An optional reference to an index of relevant documents for an application

Copyright Notice: An optional reference to the Copyright information for an application

Disclaimer: An optional reference to a Disclaimer for an application



Data Source Reference: An optional reference to a description of the data sources, to be used in reports with results of the application.



Chapter 5: Detail Pages

The Detail Pages present a detailed overview of information on the selected tree item.

The Detail Pages show (generated) HTML documents, like an Internet Browser, with hyperlinks and a back and forward button. If the text refers to a tree item, clicking the hyperlink means this item is activated. If the text is the label of a property, a dialogue is presented related to this property.

5.1 General

This page presents the most relevant properties of a tree item and its related domain and values units (if applicable). The following example shows the General page for the tree item: *Geography/RegionalUnits/Province/Shapes/area*



Figure 5.1: General (G) detail page



This Detail page shows:

- The full name, status, label, description and values type of item and if configured the class diagram to be used for classification of the data.

And, if the tree item is a data item:

- A calculation rule (expression) for a data item for which an expression is configured. The ParseResult and CacheEntry are based on this calculation rule.
- A storage for a data item read from a data source, with an indicator if the storage is ReadOnly (label ReadOnly = 1) or read and write (label ReadOnly = 0) and optional a SqlString.
- The Domain Unit for which the item is available, including the element type, if relevant the geographic projection and the range (nr elements) of the domain.
- The Values Unit in which the data item is configured, including the element type, the metric, the range of the values, the number of elements and, if configured, the classification scheme for the values unit.

5.2 Explore

The Explore detail page shows the name, description and storage type of the items in the NameSpace of the selected tree item. The following example shows the Explore detail page for the tree item: *Units*

G eneral ∑=n V <u>a</u> lue Infr	Stop Befresh Explore Properties Metadata ∑=n Statistics o B Configuration S XML Source Descr
<u>Units</u>	
Attractivity	/Units
<u>AttrPerHa</u>	/Units
<u>BcUnit</u>	/Units
<u>BetaRange</u>	/Units
<u>claimHa</u>	/Units
<u>claimHa2</u>	/Units
<u>Cm Year</u>	/Units
<u>DemandUnit</u>	/Units
Dm	/Units
Eur	/Units
<u>Eur Ha</u>	/Units
<u>Eur M2</u>	/Units
Ha H D'E	/Units
HaDitt	/Units
IterKange	/Units

Figure 5.2: Explore detail



5.3 Properties

This page shows all properties of a tree item. The following example shows a part of the properties detail page for the TreeItem: *geography/RegionalUnits/province/shapes*

← 	p ®efresh ore Properties № Metadata Σ=∩ <u>S</u> tatistic 3 Configuration 1 2 XML № Source Descr	:5
area		Â
CLASS	AbstrDataItem	
<u>DomainUnit</u>		
DomainUnit FullName	/Geography/RegionalUnits/Province/Shapes	
ValueComposition	single	
<u>ValuesUnit</u>	Meter2	Ξ
ValuesUnit FullName	/Units/Meter2	
CLASS	TreeItem	
CalcSchema		
<u>CaseDir</u>	$C:/GeoDMS/ProjDir/lus_demo/cfg/demo/Geography$	
<u>cdf</u>		
ConfigFileColNr	17	-
<u>ConfigFileLineNr</u>	275	
ConfigFileName	C:/GeoDMS/ProjDir/lus_demo/cfg/demo/Geography.	

Figure 5.3: Properties detail page

The Properties page shows all relevant properties of the selected item, including system properties, indicated by the keywords CLASS. By double-clicking on a property row, a dialogue is activated with the whole text of the property and its current value, as shown in the following example for the property full name:

FullName		
/Geography/RegionalUnits/Province/Sh	apes/area	
	<u>O</u> k	Cancel

Figure 5.4: Textbox presenting the full name of the selected tree item

This text box can be used to copy information to the Windows clipboard. In the administrator mode (see chapter 4, menu option Tools > Options > Administrator mode), the textbox can also be used to set values for some properties. This



functionality is only advised for experienced users, as setting incorrect values for properties can create an unstable system, resulting in multiple errors.



5.4 Metadata

For more information on a tree item, an URL property can be configured that refers to a document on the local machine or on the web. The document (which can be a .html file or any other file format that is supported by Internet Explorer and which application is installed on the local machine, like MS Excel, MS Word, etc.) is presented in the detail page Metadata. An example for the RuimteScanner item: /StudieGebieden/NI2008/brondata/Beleid/Ruimte/STREEKPLANNEN/streek10



The metadata detail page can also be used to specify the export settings for exporting map viewports to bitmaps. Open the metadata detail page on the item: *ExportSettings*

← → ⊗ ۞ ⊼ × <u>B</u> ack Forward Stop <u>R</u> efresh Add Remove	
General Q Explore Properties Metadata	
∑=n Value Info	
Size	*
Paper size Orientation Margins(cm)	
map window size 💌 🖸 portrait top: 2 bottom: 2	
🔿 🔽 landscape left: 1.5 right: 1.5	
width: map window width cm	
height: map window height cm	
Scale	
user defined scale	
1 to: 1000000	
Quality	
Increasing the print quality increases the number of resulting files.	
Dots per inch (dpi) View distance factor, paper compare to screen Subdots per paper dot	
$\begin{array}{c} & & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ & & \\ \end{array} \end{array} \end{array} $	
300 * 300 ▼ 1 ▼ 1 ▼	
Save Settings	~

Figure 5.6: Metadata detail page for item ExportSettings



In this dialogue the following options can be configured:

Size

- Paper size:

The paper size defines the export area of the resulting bitmap. The following options are available:

- map window size: the export area is the area of interest visible in the map view
- A specific paper size: the export is based in the center point of the area of interest in the map view and the selected paper size.
- User-defined: the width and height options become enabled. The export is based in the center point of the area of interest in the map view and the specified paper width and height.

- Orientation:

For specific and user-defined paper sizes, this option indicates if a landscape or portrait export is desired.

- Margins:

For specific paper sizes, margins can be set. The margins influence the width and height of the resulting bitmap.

Scale

The user can define the scale of the resulting map view with the following options:

- **User-defined:** the 1 to .. option becomes enabled to indicate that 1 cm in the map is the specified value in cm's in the real world
- **Based on map windows:** the same scale is used as in the exported map window
- **A specific scale:** the available options are the 'optimal' scale levels for the background map layers. It is recommended to use one of these scale levels, for the nicest map results.

Quality

- Dots per inch(dpi):

This quality setting indicates how many dots will be printed per inch, based on the allowed dpi of the printer. Increasing this number results in better quality maps (if supported by the printer), but also results in more/larger bitmaps. MS Office products like PowerPoint usually assumes images to be around 100 dpi, this means the image size needs to be adjusted if files with larger dpi are imported.

- View distance factor:

A factor indicating if the result is to be seen at the distance of a screen of e.g. of a poster, which is usually looked at from a larger distance. A large view distance factor means the objects in the map are presented larger. The default value is 1.

- Subdots per paper dot:

For future use, the default value is 1

After adjusting these values, activate the save settings button to save the settings for the current session. If the application is ended, these settings are not saved to the configuration. The next time the application is run, the original settings apply again.



5.5 Statistics

This detail presents general statistics about a numeric data item. The example presents the detail page for the item: Current_Situation/Current_landuse/predominant_2010

⇔ ⇒ <u>B</u> ack Forw	ard Stop Befresh
😭 <u>G</u> eneral	🔯 Explore 📓 Properties 🕼 Metadata Σ=n Statistics
∑=n V <u>a</u> lue Info	o 🖆 Configuration 🖆 XML 🕥 Source Descr
Statistics	for /Current_Situation/Current_landuse/predomina
ValuesType	UInt8
Count :	351000
Maximum :	8
Minimum :	0
Sum :	1990307
Average :	5.67039031
Variance :	5.68713808
StdDev :	2.38477552
Nr Nulls :	0
Nr Values:	351000

Figure 5.7: Detail page Statistics

In this page the follo	wing statistics are presented:
ValuesMetric:	the metric of the values unit of the data item (if specified)
ValuesType:	the value type of the values unit of the data item
Count:	number of items of the data item
Maximum:	maximum value of the data item
Minimum:	minimum value of the data item
Sum:	sum of all values of the data item
Average:	average value of the data item
Variance:	variance of the data item
StdDev:	standard deviation of the data item
Nr Nulls:	number of missing data elements of the data item
Nr Values:	number of non-missing data elements of the data item



The Statistics is only shown if the data item is valid (as it can take some time to update a tree item). If the item is not yet calculated, a message is shown that the data item is invalidated. In that case, press the Ctrl-U combination to update the tree item first. If the item is not a data item or not numeric, a message is shown which indicates the statistics cannot be shown.

The results in the Statistics view can differ slightly from calculated aggregated values. The Statistics view calculates all present values in a float64 format. If an aggregation is performed on a float32 data item, the results are round off after the calculations to a float32 format.

5.6 Value Info

The construction of a data value in the Table or map view is activated by selecting a cell in the Table or by activating the I-tool in the map and selecting a certain grid cell in the map. If the value info page is the active detail page, all the steps are presented on how a data value is constructed from the source data and the performed calculations:



Figure 5.8: construction of a data value in the data grid view for the tree item: /Geography/RegionalUnits/DijkRing/Shape_rel

If e.g. the cell with the value 17 is selected in the table and the detail page info value is active, the information as shown in the example is presented. This information



describes how the value is calculated and which suppliers are used. The next sentences indicate the values of the suppliers. Use the hyperlink to find out how these values are calculated and what their suppliers are.

5.7 Configuration

The configuration tab shows the configuration syntax of the selected item (and if available, it's subitems). The following example presents the configuration detail page for the tree item: *Units/Eur_Ha*

← Back	⇒ Forward	× Ston	(†) Refresh						
<u>B</u> uck [™] <u>G</u> en	eral 🛛 🖾	Explore	Properties	🕜 <u>M</u> et	adata	∑=n <u>S</u> tatistics	5		
Σ=n Value Info Configuration Source Desc						Source Descr			
unit <float32> Eur_Ha:</float32>									
Expr = "Eur / Ha";									

Figure 5.9: Detail page Configuration

More information on how to configure with the GeoDMS can be found in the modeler's guide on http://www.objectvision.nl/geodms/modellers-guide.

5.8 XML

The XML tab shows the XML configuration syntax (.xml) of the selected item (and if available, it's subitems). The following example presents the XML detail page for the tree item: Units/Eur_Ha

 ← → ⊗ ⊉ <u>Back</u> Forward Stop Befresh [™] <u>G</u>eneral [™] Explore [™] Properties [™] <u>M</u>etadata Σ=n <u>S</u>tatistics Σ=n Value Info [™] <u>C</u>onfiguration [™] <u>XML</u> [™] Source <u>D</u>escr 							
xml version="1.0" encoding="windows-1252"?							
<doctype name="DMS"></doctype>							
<unit <="" name="Eur_Ha" td=""></unit>							
ValueType="Float32">							
<expr>Eur / Ha</expr>							

Figure 5.10: Detail page XML



5.9 Source Description

This detail page describes, if relevant, information about all sources used to calculate a data item. If a source property is configured for a data item, this information is presented, of not the data sources names(files) is presented. An example is shown in the next figure:

← <u>B</u> ack	⇔ F <u>o</u> rward	🗴 🗗 Stop Refresh							
r	<u>G</u> eneral	🔍 Explore	Properties	🕐 <u>M</u> etadata	∑=n <u>S</u> tatistics				
∑=n V <u>a</u> lue Info		[∰ <mark>] _</mark> o	nfiguration	marka ML	Source Descr				
 D:/PBL/SourceData/Cursus_voorjaar_2017/Geografie/corop_2011.shp D:/PBL/SourceData/Cursus_voorjaar_2017/Geografie/GemeenteGrenzen_2012.shp 									

Figure 5.11 Detail page Source Description



Chapter 6: Introduction

6.1 Data visualization

The set viewers in the GeoDMS GUI are used to visualize source data and calculated model results. As most data in the applications are geographically related, the main viewer is the map view. This map view is configured as the default view for all items that are geographically related. More information on the map view can be found in chapter 7. The default view is activated by double-clicking on a tree item, by selecting a tree item and pressing the Enter key or by activating the default view action from the main or pop-up menu. The default viewer for data items is indicated in the Treeview by the presented icon (see paragraph 3.2).

For data items that cannot be visualized in a map (like a parameter), the default view is the Table. All data items can be visualized in a Table, by activating the Table view main or pop-up menu item. The Table is described in detail in chapter 8. The third type of view that can be applied to primary data is the histogram view. This view is not configured for any item as the default view but can be activated with the histogram view main or pop-up menu item. The histogram is described in chapter 9.

As well as the views for the primary data, the GeoDMS GUI also offers views on the configured calculation and model logic. Therefore, the so-called process schemes are implemented, allowing the user to get a scheme of the subitems, suppliers and calculation logic of a tree item. These process schemes are described in detail in chapter 10.

All views are positioned in the view area of the application. The first view is always opened maximized. Be aware that the minimum, restore/maximize and close buttons of this view are located at the top right corner of the window in the main menu bar, as shown in the next figure:



Figure 6.1: Map view



If a second view is opened, this view is opened maximized if the other views are also maximized. Otherwise, the window is opened in the normal Windows state.

Each viewer has its own set of tools in the taskbar when the view is activated. In Figure 6.1 the tools of the map view are presented. All views are listed in the Window main menu option. With this menu option the views can be tiled, cascaded and all windows can be closed.


Chapter 7: Map View

7.1 Introduction

The map view presents data items that can be geographically located. Each map view has a projection, indicating the coordinate system. In Dutch applications, the projection used is usually the "Rijks Driehoek (RD)" coordinate system for all geographically related data items (other coordinate systems are possible, but the source data is usually in RD Coordinates). A map view consists of layers, each layer is related to one or more data items. All geographically related data items using the same projection can be combined in the same map view window. They can also be opened in multiple separate map views. The number of opened map views is not limited.

In the example of figure 6.1 a map view is presented with three layers:

- Two reference layers with province boundaries and with a top100 grid.
- A dominant land use thematic grid layer.

In paragraph 7.2 the available layer types for a GeoDMS map view are described. A map view can be activated from the Treeview by selecting tree items that can be geographically related. These items are indicated with a map icon (2).

A new map can be created or a layer can be added to an existing map by selecting a tree item and activating one of the following actions listed in the table. The result of the action, based upon whether there is already an active map view opened, is described.

Action	No active map view	Active map view		
Double click on selected tree	New map window	Layer opened in active		
item		map view with same		
		coordinate system		
Enter key on selected tree	New map window	Layer opened in active		
item		map view with same		
		coordinate system		
Main/pop-up menu option	New map window	Layer opened in active		
Default View		map view with same		
		coordinate system		
Main/pop-up menu option	New map window	New map window		
Map View				
Ctrl-M on selected tree item	New map window	New map window		
Drag and drop to view	New map window	Layer opened in active		
area/active window		map view with same		
		coordinate system		

A reference grid layer can be configured as a background layer. This means in all map views this layer is visualized automatically when the view is created (see the modeler's guide for how to configure a default layer).



7.2 Layer types

In a map view, layers can be visualized in different ways. Within the GeoDMS a difference is made between:

Reference/background layers:



Figure 7.1: Examples of reference/background layers with polygons/labels and grid data

Layers that are used to refer in an intuitive way how the data is to be visualized. Reference layers are usually:

- topographic polygon layers (showing the boundaries of areas like in the example above), sometimes with a label configured (as in the example)
- Grid layers which can present different detail information at different zoom levels.

In GeoDMS applications one or a set of reference layers is often configured as default layer (see the modeler's guide for how to configure a default layer). The default layer (set) has by default one entry in the legend.

Attribute data layers:

Layers use to present data related to a geographic domain. This domain consists of geographic objects, which can be grid cells, polygons, arcs or point as in the following examples:



Figure 7.2: Examples of attribute data layers with grid, polygons, arcs and points data

In these layers, the features (grid cell, polygon, arc, point) are visualized with one or multiple visualization styles (colors, symbols, size etc.). The possible styles are dependent on the layer type. The style values refer to classes in a classification scheme. This implies that a palette (e.g. color, size, symbol) and, if the data item is not yet classified, a classification is needed to visualize a data item as a thematic layer. If no classification is found for the data item or its values unit (see chapter 10 for more information), a data item cannot be visualized thematically.

Layers can be activated with the actions listed in paragraph 7.1. The grid layer type is activated for each numeric data item with a grid domain as domain unit. For the vector data types (polygon, arc and point), the geographic format specified for the values unit of the feature data item, determines if the data is visualized as point, arc or polygon (see the modeler's guide how to configure these values types).



A specific theme of a layer is a text label. Text labels can be used for polygon and point layers.



Figure 7.3: Examples of labels for polygon and points layers

7.3 Active Layer

The active layer is an important concept in each GeoDMS map view. The active layer is the layer on which the layer-specific (toolbar) functions are executed.

A layer can be activated from the legend (see 7.5). In this legend the active layer is indicated by a blue background color in the title as in the next figure (the last column contains the counts):

predominant_2010					
[LUclasses]					
residential	11864				
industrial	3229				
recreation	2421				
agriculture	99588				
nature	17699				
buildinglot	979				
infrastructur	e372				
water	113235				
exterior	101613				

Figure 7.4: Examples of an active layer in the Legend

The user can switch between active layers by clicking on the layer title. There is always only one active layer (activating one layer deactivates all other layers). By default, the last layer added to the map view becomes the active layer.

7.4 Tools

When a map view is then activated, the set of specific map view tool buttons is presented in the toolbar. By default, the 'Zoom in'-tool is activated, as this is often the first action performed. For the neutral state (arrow that performs no action on the map view) deactivate the zoom or selection state by re-clicking on the same tool.

The following buttons are available to adapt or query the map view (not all tools might be visible for a specific project, this can be configured in the <u>config.ini</u> file):

۲

Fit to all layers: action to enlarge or reduce the zoom level and pan the area to make the extents of all layers fit in the active map view.



 \geq

Fit to active layer: action to enlarge or reduce the zoom level and pan the area to make the extents of the active layer fit in the active map view.



Zoom in: zoom in tool, presenting the cursor as a magnifying glass with a plus sign, which can be used to zoom in, in two ways:

- Click with the left mouse button at the top left corner of the requested area of interest. Keep the left mouse button pressed and move the mouse to the bottom right corner, a rectangle is drawn on the map. Release the mouse button and the map zooms into the requested rectangle.
- Click with the left mouse button on a position in the map and release the button. The map is zoomed in with a fixed zoom factor and the cursor position as center.

The Zoom in tool is configured as default tool. The neutral state (no tool active) can be achieved by activating this button.

Θ,

Zoom out: zoom out tool, presenting the cursor as a magnifying glass with a minus sign, which can be used to zoom out until the full extent of the map is reached. Click with the left mouse button on a position in the map and release the button. The map is zoomed out with a fixed zoom factor and the cursor position as center.

${}^{(0)}$

Pan: pan tool, presenting the cursor as a semi-transparent hand sign, which can be used to move the presented layers. To pan, click with the left mouse button at a position in the map, keep the left mouse button pressed and move the mouse to the requested direction. Release the mouse button and the requested new area of interest is drawn.

0

Info: information tool, presenting the cursor as an arrow with an i-sign, which can be used to query individual features in the map of the active layer (see 7.3). To query the values of individual features, click with the left mouse button on the requested grid cell, point, arc or polygon. The feature is shown in a new color. The information of this feature is shown in two ways:

- In the legend, the values of the attribute of the active layer and all grid attribute layers are presented in front of the values unit or in a separate line.
- If the value info detail page is visible, the whole path for how the value in the map view is constructed is presented (see paragraph 5.6 for more information on the value info Detail Pages).

The information tool is related to the active cell in a data grid of the same domain unit as information is requested from in the map view.

The following six tools are used to (de)select objects. The selected features of polygons, arcs and points are colored light blue. For grid cells, a hedge style for both interior as the border is used to indicate selected cells.



Selected features are by default added to the earlier selection. Keep the Control key pressed to deselect features. Activate the 'Select none'-tool to reset the whole selection in the active layer.

Toggle layout: action to toggle between three layout options of the map view. By default, the legend and the overview map are visible in each map view. With the toggle layout tool, the user can select between three options:

- Legend and overview map visible (default)
- No legend and no overview map visible
- Only legend visible, no overview map

The tool presents a picture of the layout that will be presented if the tool is activated. The default tool shows an empty layout of the view area. If the tool is activated no legend and no overview map will be presented. The tool itself is now changed to the following picture:

It shows a legend area in the right part of the view area. If the tool is now activated, a legend is presented but no overview map. The tool is again changed to the following picture:

It now shows both a legend area and an overview map area. If the tool is now activated, a legend and an overview map are presented (the default status of the map view). The tool is changed to its original picture.

Toggle palette: action to toggle between three options of showing/hiding palette information the legend. By default, palette information is presented in the legend if the number of entries in the palette is less or equal than 32.

With the toggle palette tool, the user can select between three options:

- show palette information for each layer with palette information in the legend
 show palette information for the active layer with palette information in the
- legend
- show no palette information for each layer in the legend

Activate the button to select the next option. The picture of this button will not change.



Toggle Needle Controller: action to toggle between showing and hiding a horizontal and vertical grid line, called a needle controller, in the map view. These grid lines can be used for accurate navigation (X and Y coordinates are always visualized in the toolbar).



Toggle Scale bar: Action to toggle between showing and hiding a scale bar in the bottom right corner of the map view.



Copy visible area: action to copy the visible contents of the active map view to the clipboard. In case the legend is visible, this legend is also copied to the clipboard. The legend can be made (in)visible with the Toggle layout button.



Copy full legend: action to copy the full contents of the legend to the clipboard. The size of contents of the clipboard is limited, if the data to be copied exceeds the maximum size of the clipboard, an error is generated.



Export viewport: exports the active viewport to one or a set of bitmaps, using the specified export settings. See paragraph 5.4 for information on how to edit these settings. All viewports can be exported by using the File > Export Viewports menu option.



Fit to selected features in active layer: action to enlarge or reduce the zoom level and pan the area to make the extents of the selected features in the active layer fit in the active map view.



Select individual feature: a select tool to select individual features in the active layer. A ball pen is presented, with which individual features can be selected (left mouse click).



Select rectangle: a select tool to select features with a rectangle in the active layer. A ball pen is presented, with which features can be selected. Move the cursor to the top left corner of the requested rectangle and press the left mouse button. Keep the button pressed and move the mouse to the bottom right corner, a rectangle is drawn on the map. Release the mouse button, all features in this rectangle are now selected.



 \diamond

Select circle: a select tool to select features with a circle in the active layer. A ball pen is presented, with which features can be selected. Move the cursor to the center point of the requested circle and press the left mouse button. Keep the button pressed and move the mouse to the requested size, a circle is drawn on the map. Release the mouse button, all features in this circle are now selected.



Select free area: a select tool to select features with a user-drawn area in the active layer. A ball pen is presented, with which features can be selected. Move the cursor to the first point of the requested area and press the left mouse button. Move the cursor to the next point and press again. Continue these steps until the complete area is drawn. Double click on the last point to select the features in this user drawn area.



Select contiguous regions: a select tool to select features within a contiguous region.



Select all: action to select all features in the active layer. Activate the tool to select all features in this layer.



Select none: action to deselect all features in the active layer. Activate the tool to deselect all features in this layer.



Show only selected: action to toggle between showing only the selected records or showing all records in the map view. In case all records are shown, the selected records ale colored in the selection color. In case only the selected records are shown, the background color of the layer in the legend becomes the selection color.



7.5 Legend

The legend of the map view has two functions. The first function is the legend function for a map, explaining which layers occur in the map including their values units and, if applicable, their classifications schemes. The second function is to activate layer specific functionality of the layers in the map view.

An example of a legend for a map view is presented in figure 7.5:



Figure 7.5: Map view legend with an overview and two layers

The upper part of the legend presents an overview map with the full extent of the contents of the configured default layer(s). See the modeler's guide for how to configure a default layer. The purple transparent area indicates the visible part in the map view. The overview is used for a geographic reference, but can also be used for navigating by dragging the purple area. The overview window is default visible but can be made invisible with the pop-up menu from this Legend (see 7.5.1 pop up menu).

All layers in the map view are presented in the legend. The sequence indicates the drawing order. The layer at the bottom is drawn first, the following layers are drawn next, so the layer at the top of the legend is drawn above all layers.

Each layer in the legend is presented with a title (the name of the data item that was requested, or in case this item has a label property configured, its label). Below the title, the values unit of the data item is shown. If the information tool is used, the



value for the specific object selected in the active layer in the map is also presented in this line.

For layers with a classification scheme configured, the palette colors, classes, labels and a count of the number of entries in the class are default shown in the legend control, in case the number of entries is less than 15. If symbols are defined in the scheme, these symbols are also presented. With the pop-up menu (see 7.5.1.) the user can hide or visualize this palette information for the layer in the legend.

With the button, the palette information can be shown for no, the active, or for all layers. The width of each column can be adapted. Click with the left mouse button on the line between the columns, keep the mouse down (a different cursor appears) and drag the width of each column to the requested size.

The colors, labels and class values of calculation schemes can be edited from the legend. To edit a color, double-click on the color in the legend for a Windows color dialogue. To edit the class values or labels, click on the specific cell in the legend. Type a new value or use the F2 key to edit the current value. To edit other aspects of the scheme, like the number of classes, use the Edit Palette pop up menu option for the palette dialogue (see chapter 10).

A layer in the map view and related in the legend has a visible or hidden state. If a layer is hidden in the map view, this is shown in the legend with a grey color. The user can toggle between the hidden and visible state by double-clicking on the layer title. By default, a layer is always visible.

With the Ctrl key pressed and the arrows up and down and left and right, it is possible to scroll in the legend. The Ctrl-Home and Ctrl-End key combinations move directly to the top and end of the legend. Scrolling becomes relevant if the legend information does not fit in the visible area of the screen.

Layer-specific functions and some general map settings can be activated from a popup menu, which is shown if a user clicks with the right mouse button on the layer in the legend. The options presented are described in subparagraph 7.5.1.

7.5.1. Pop up menu

Activating the pop-up menu on a layer presents the following menu:

	Hide LayerControl for predominant_2010	
	Set LayerControl Font	>
	Bring z-Position of Layer	>
	Remove Layer	
	Show Statistics on predominant_2010	
	Activate Treeltem of Layer Aspect	>
	Zoom 1 Grid to 1 Pixel	
~	Show Palette	
	Edit Palette	

Figure 7.6: pop up menu



The following options are available

- Hide LayerControl for layer

The layer is not visualized in the layer control (e.g. background layers can be made hidden when exporting a legend). A right mouse click on the layer control on an empty area offers the option to make the hidden layers visible again.

- Set LayerControl Font:

Three options are available for the size of the layer font in the legend. The default option is small. The user can set the font size to medium or large.

Bring z-Position of Layer:

The sequence of layers in the legend corresponds to the drawing order in the map view. This order can be changed with the four submenu options. Grid layers drawn above other layers are visualized transparently.

Only the relevant submenu actions are enabled for the user:

- **To Top:** The layer will be drawn above all other layers. In the legend, the layer is moved to the top. The option is only available in case the layer is not yet the top layer in the drawing order.
- **To Bottom:** All other layers will be drawn above this layer. In the legend, the layer is moved to the bottom. The option is only available in case the layer is not yet the last layer in the drawing order.
- **Up:** The layer is positioned one step higher in the draw order. In the legend, the layer is moved one place higher. The option is only available in case the layer is not yet the top layer in the drawing order.
- **Down:** The layer is positioned one step lower in the draw order. In the legend, the layer is moved one place lower. The option is only available in case the layer is not yet the last layer in the drawing order.
- The sequence can also be adapted for dragging and dropping the layer.
- Remove layer: The layer is removed from the map view.

Based on the type of layer some additional layer specific options are available:

- **Show Statistics on** *layer***:** presents a dialogue box with the same statistics as presented in the Detail page, Value Info (see 5.5)
- **Classify with:** if one or more classifications are available for the data item shown as attribute layer, these are presented here. The user can select from the relevant classifications.
- Activate TreeItem of Layer Aspect: for each aspect the thematic data and, if used, class breaks and aspect values can be activated. The submenu's present the relevant aspects and items and their parents. With a left mouse click, the requested item becomes activated. The dominant ggModel layer has only a brush color aspect, so only this Activate option is presented in the example.
- Select SubLayer(s), (not for grid layers); the different style aspects used to draw a layer can be activated separately. The style aspects differ for the different layers types. Therefore, the set of submenu options differ per layer type. A ✓ indicates a style aspect is active (visible). For polygon and point layers, labels can be activated with the Select SubLayer >Label > Visible menu option.
- **Zoom 1 Grid to 1 Pixel (only for grid layers):** The layer is zoomed to the level at which each grid cell corresponds to one pixel. This is often the most elegant level to present a grid.
- Show Palette (only in case a palette item is used for visualization): This option toggles between showing and hiding the palette and label information in the legend of the classification scheme used for the data item. A
 character before the menu option indicates the information is shown.



- Edit Palette

This option activates the edit classification dialogue (see chapter 10) to edit the classification/palette used to draw the layer.

The Edit classification dialogue presents a table, the table tools (see chapter 8) can be used for this table.

The pop-up menu can also be activated by right mouse clicking in the map view. The layers visible in the map view are shown and the similar functions are available for these layers and for the general map view/legend options.



Chapter 8: Table

8.1 Activating a Table

The Table presents data items or a set of data items of the same domain unit in a Table. All data items can be visualized in Table. The Table is the default view for items that cannot be visualized in a geographic view, these items can be:

- Data items for which the domain unit cannot be georeferenced (parameters or other data items for which there is no geographic domain, like the label data item of a classification). These items are indicated by an \blacksquare icon.

- Containers with data items as subitems (first level subitems). The first data item of this container determines the domain unit of the Table, all data items that have this same common domain unit are visualized in the grid. These items are indicated by an 📰 icon.

As with the map view, a new Table can be activated for a tree item, or the tree item can be added to an already opened Table (if this opened view is of the same domain unit as the requested data item). The following table shows the possible actions to visualize a tree item in a Table and the results of the actions:

Action	No active Table	Active Table with	Active Table for
	for the requested	same domain unit	another domain
	domain unit	as requested data	
		item	
Double click on	New Table window	Data item or	New Table window
selected tree item	with the requested	subitems at the	with the requested
(only if the Table is	data item or all the	first level with the	data item or all the
the default viewer,	subitems at the	same domain unit	subitems at the
indicated by the 🛄 or	first level of the	are added to the	first level of the
🔄 icon)	found domain.	active grid.	found domain.
Enter key on selected	New Table window	Data item or	New Table window
tree item (only if the	with the requested	subitems at the	with the requested
Table is the default	data item or all the	first level with the	data item or all the
viewer, indicated by	subitems at the	same domain unit	subitems at the
the 🖽 or 🔜 icon)	first level of the	are added to the	first level of the
	found domain.	active grid.	found domain.
Main/pop-up menu	New Table window	Data item or	New Table window
option Default View	with the requested	subitems at the	with the requested
(only if the Table is	data item or all the	first level with the	data item or all the
the default viewer,	subitems at the	same domain unit	subitems at the
indicated by the 🛄 or	first level of the	are added to the	first level of the
🔄 icon)	found domain.	active grid.	found domain.
Main/pop-up menu	New Table window	New Table window	New Table window
option Table View	with the requested	with the requested	with the requested
	data item or all the	data item or all the	data item or all the
	subitems at the	subitems at the	subitems at the
	first level of the	first level of the	first level of the
	found domain.	found domain.	found domain.
Ctrl-D on selected	New Table window	New Table window	New Table window
tree item	with the requested	with the requested	with the requested
	data item or all the	data item or all the	data item or all the
	subitems at the	subitems at the	subitems at the



	first level of the found domain.	first level of the found domain.	first level of the found domain.
Drag and drop to view area/active window	On empty view area: New Table window with the requested data item or all the subitems at the first level of the found domain	Data item or subitems at the first level with the same domain unit are added to the active grid.	Another view: Not allowed to drop the item.

8.2 Table

Activating the Table for the tree item: *Geography/RegionUnits/Province/VAT* results in the following table:

OMSClient - demo.dms - [VAT: 13 re	cs]	(maning)		1 marting	r Treaster	Country I Trees	Aug Trinategy Trinate	
<u>File Edit View Insert T</u> ools	<u>W</u> indow <u>H</u> elp							_ 8 ×
12 PL 🖬 🗖								
E demo	id Nr	area [m^2]	BrushColor	Provinces La	Provinces La	⊕ ⇒	8	
⊡ ⊡ Geography	0 (none) 0 (none)	2.69678E+09	8421504	none		Back Forward	d <u>S</u> top <u>R</u> efresh	
	1 (Groningen1 (Groni	ngen 2.40043E+09	16777215	Groningen	Groningen	General	🔍 Explore	Properties
Σ=n rdc_meter	2 (Friesland) 2 (Friesla	nd) 3.53551E+09	8454143	Friesland	Friesland	🕜 <u>M</u> etadata	∑=n <u>S</u> tatistics	∑=n V <u>a</u> lue Info
	3 (Drenthe) 3 (Drent	ne) 2.68036E+09	65535	Drenthe	Drenthe	P Configura	tion 😭 🔀 ML	Source Descr
🛱 🚎 RegionalUnits	4 (Overijssel) 4 (Overi	ssel) 3.40466E+09	33023	Overijssel	Overijssel			*
	5 (Gelderland5 (Gelde	land 5.11616E+09	255	Gelderland	Gelderland	VAT		
	6 (Utrecht) 6 (Utrec	t) 1.44282E+09	16711935	Utrecht	Utrecht			
Nr Nr	7 (Noord-Hol7 (Noord	-Hol2.8572E+09	8388783	Noord-Hollar	Noord-Hollan	<u>FullName</u>	/Geography/RegionalUni	ts/Province/VAT
area	8 (Zuid-Hollar8 (Zuid-	Iolla 3.03733E+09	8388708	Zuid-Holland	Zuid-Holland	ProgressState	DataReady at 2	
EushColor	9 (Zeeland) 9 (Zeelar	d) 1.81475E+09	13107250	Zeeland	Zeeland	Label		
🗈 👰 LabelMap	10 (Noord-Br10 (Noo	d-Br5.01915E+09	16711680	Noord-Braba	Noord-Braba		This is the entity of the 1	2 provinces in the
🕀 📻 Shapes	11 (Limburg) 11 (Limb	urg) 2.20924E+09	8388608	Limburg	Limburg	Descr	Nederlands (0=Exterior))
DijkRing	12 (Flevoland12 (Flev	and 1.47067E+09	4194304	Flevoland	Flevoland	ElementType	UInt8	

Figure 8.1: Table View

The mentioned tree item is a domain unit with 13 elements. All subitems have VAT as domain unit. Therefore, all these subitems are shown in the table.

The first column shows the index number(id). The other columns contain the data items requested. Some columns are colored a darker grey, indicating their values cannot be edited. Columns with values that can be edited are colored light grey.

The width of the columns can be adapted by moving the mouse to the header row (in light grey background color with the labels of the presented data item), on the border between two columns. Click with the left mouse button, keep this button pressed and move the mouse to the left or the right to change the size of the columns.

The sequence of columns can be adapted with drag and drop on the column header of a label. Click with left mouse button on a header, keep the mouse pressed and move the mouse to the requested position.

In the table, a cell or a column can get the focus. Click on a cell or a column header to set the focus. Also, a focus rectangle can be used to set the focus to multiple cells. Therefore, first set the focus to one cell and use the arrow keys to enlarge the focus rectangle (colored black). Also in a focus rectangle, there is always one focus cell (colored blue).



If the Detail page Value Info is active, the whole path of how this selected data value in the Table is constructed is shown (see paragraph 5.6). The focus cell in the table is related to the information tool in the map view. If information is requested on a feature in the map view, the cell of the record of this feature receives the focus and vice versa.

A column receives the focus by a left mouse click on the label of the column in the header row. With a right mouse click on the label a pop-up menu for the column is activated, with the options:

- Sort on data item name: To sort values ascending or descending
- Relative Display: to present the numeric values as percentage of the total
- **Copy** *data item name:* To copy the values of the item to a new data item with the name: *data item name* + Copy + *SequenceNr*, mainly relevant in classifications
- **Remove** *data item name*: to remove the selected column from the Table.
- **Ramp Values**: to ramp the values of a distribution, mainly relevant in classifications. This option is only available for not derived, numeric data items with more than one entry.

8.3 tools

If the Table is active, the following tools are available in the toolbar:

E

Copy text: Copy the highlighted contents of the table as semicolon delimited text to the clipboard. String attributes are quoted.

To highlight a cell, click on the cell with a left mouse click. Use the arrow keys to enlarge or diminish the set of highlighted cells.

To copy the whole table:

- 1. Highlight only one cell, a single highlighted cell will copy the whole table.
- 2. Un-highlight all cells, click with the left mouse click on a highlighted cell and press the Escape key.



Copy image: Copy the visible contents of the active table as an image to the clipboard.



Save to csv: Save the highlighted contents of the table as semicolon delimited text to a file. String attributes are quoted. The path of the file is indicated by a dialog.



Group by: Group the data by the unique values in the selected column.



Show first selected row: Action to scroll the table to present the first selected row(s) in the visible part of the table.



ŧ

Select focus cell range: Select the records for which cells are part of the cell range in the table. The selection will also apply to the map view and vice versa. The selection color is light blue.



Select all: Action to select all rows in the table. The selection will also apply to all map views.



Select none: Action to deselect all rows in the table. The selection will also apply to all map views.



Show only selected records: Action to toggle between showing only the selected records or showing all records in the table.



Chapter 9: Histogram View

9.1 Histogram view

A histogram presents a graph with a frequency distribution of the occurring data values in a data item. If the data item is not classified (the value type of the values unit is not uint8), a classification is needed before a histogram can be made. Only the class values are used for the histogram view, not the palette colors or the labels. The following example shows the histogram for the data item: *Current_Situation/Current_landuse/predominant_2010*



Figure 9.1: Histogram view

The values on the x-axis correspond to the land use classification. The y-axis shows the count of the number of occurrences in the domain of the original data item, in this case, land use classes. The full name of the presented data item is shown in the graph title.

A histogram can be activated with the main or pop-up menu Histogram View (Ctrl H) if the tree item is a numeric data item (not a parameter).



Chapter 10: Insert Classification and Palette

10.1 Classifications and palettes

Classifications are used to classify numeric data items into a set of classes. A classification is mainly used in primary data viewers to group relevant sets of elements. These groups are visualized using the same visualization style. In the GeoDMS GUI themes (colors, sizes, symbols and styles) are used to visualize classes of an attribute layer in a map view. The classification and palette editor can for the moment only be used to specify colors (other themes need to be configured in the dms configuration files, see the modeler's guide). The set of colors for each class in a classification scheme is called a palette. Often also a label is requested for a class in classification that, if used, is shown in the legend of a primary data viewer.

The next table shows where classifications in the GeoDMS GUI are used, depending on the requested data item:

Data type	Thematic map layer	Histogram	Export to bitmap
Unclassified one dimensional numeric data item (value type int8, (u)int16/32, float32/64)	Classification: obl Palette: obl Label: opt	Classification: obl Palette: nu Label: nu	Classification: obl Palette: obl Label: nu
Classified one dimensional numeric data item and Boolean (value type uint8 and Boolean)	Classification: opt Palette: obl Label: opt	Classification: opt Palette: nu Label: nu	Classification: opt Palette: obl Label: opt
Non numeric data item (value type = string)	Classification: np Palette: np Label: np	Classification: np Palette: np Label: np	Classification: np Palette: np Label: np
Point, arc and polygon data (value types (s)(d)(f)(i) point/arc/polygon)	Classification: np Palette: np Label: np	Classification: np Palette: np Label: np	Classification: np Palette: np Label: np

obl: obligatory opt: optional nu: not used np: not possible

Classifications and palettes in the GeoDMS can be configured for both data items as well as units. If a classification or palette is needed for the requested user action (as presented in the table), the GeoDMS GUI first checks for the requested data item if these are available. If not, the GeoDMS GUI checks for the values unit of the requested data item if a classification and palette is configured. In case no classification and/or palette is found for both data item and values unit, a default classification is generated.



Classifications including palettes and labels can be inserted or edited with the Insert/Edit Classification and Palette dialogue. Select the data item or unit for which a classification needs to be configured and activate the Insert Classification and Palette main or pop-up menu option (or the Ctrl F keyboard combination). Use the Edit Classification and Palette main or pop-up menu option (or the Ctrl F keyboard combination) to edit the classification and palette of a data item or unit. Be aware, if a data item has no classification configured, the Edit Classification and Palette option edits the classification configured for the values unit.

10.2 Insert Classification and Palette dialog

The editor can e.g. be activated from the legend in the map view. Activate a map view for the item: */Current_Situation/Current_landuse/LU_2010/residential* Activate the palette editor with the Edit Palette pop up menu option for this layer, the following view appears:

0	PaletteEd	itor for resid	ential			- • ×
Dor	main: lar	nduseHa9K			#Classes	9
Bri	Label	Classes [10 k	count			
	0.00 - 0.05	0	317851			
	0.05 - 0.10	0.05	725			
	0.10 - 0.25	0.1	1190			
	0.25 - 0.50	0.25	1646			
	0.50 - 1.00	0.5	2336			
	1.00 - 2.50	1	5097			
	2.50 - 5.00	2.5	4704			
	5.00 - 10.00	5	5678			
	10.00 - 25.00	10	11773			
				-		
-						

Figure 10.1: PaletteEditor for /Current_Situation/Current_landuse/LU_2010/residential

This view with the classification scheme contains a Table, as described in chapter 8. The table tools can be used for this table. This Table contains a Brush color, label, classes and count column. The count column is grey, indicating its values cannot be edited. The sequence of the columns and the width can be adapted as described in paragraph 8.2.

Classes are always increasing and connected. In the table, the start value of each class is presented. The end value is the start value of the next classes, presented in the next row. The last class is always infinite.

The pop-up menu of the table view with some different options is available for the columns of the Table. See the column description for their specific menu options.



BrushColor: individual colors can be edited by double-clicking on a specific color cell. A Windows color dialogue appears. The pop-up menu option for this column contains the following options:

Copy BrushColor	
Remove BrushColor	
Ramp Colors	
Change Color	>
Classify residential	>
Copy Table landuseHa9K	

- Copy BrushColor: to copy the color column to a new color data item, with the name of the original item, the extension Copy and a sequence number. This way color columns that cannot be edited (e.g. because read from an ODBC source) can be copied, the copy item can be edited.
- **Remove BrushColor:** to remove the column from the view
- Ramp Colors: multiple color cells can be selected to ramp the colors. Select a start and end color for the ramp, and activate this menu option. The ramp can be made for all classes or a random selection of at least two consecutive classes.
- **Change Color:** Select a color from a palette editor or set the color to fully transparent
- **Classify** *original data item*: to classify the original data item, see the class's column.
- **Copy Table** *class unit*: to copy the whole classification scheme.

Label: individual labels can be edited by activating the cell and typing a new label or by pressing the F2 function key and editing the current label. The pop-up menu option for this column contains the following options:



- **Copy Label**: to copy the label column to a new color data item, with the name of the original item, the extension Copy and a sequence number. This way label columns that cannot be edited (e.g. because read from an ODBC source) can be copied, the copy item can be edited.
- **Remove Label:** to remove the column from the view
- **Classify** *original data item*: to classify the original data item, see the class's column.
- **ReLabel**: to relabel the contents of the label column with derived labels from the class boundaries
- **Copy Table** *class unit*: to copy the whole classification scheme.



Classes: individual classes can be edited by activating the cell and typing a new class value or by pressing the F2 function key and editing the current class value. The popup menu option for this column contains the following options:

Relative Display (as % of total)	
Copy Classes	
Remove Classes	
Ramp Values	
Classify residential	>
Copy Table landuseHa9K	

- Relative Display: to present the values as % of the total
- Copy Classes: to copy the classes column to a new color data item, with the name of the original item, the extension Copy and a sequence number. This way class columns that cannot be edited (e.g. because read from an ODBC source) can be copied, the copy item can be edited.
- **Remove Classes:** to remove the column from the view
- Ramp Values: with this option, the class values can be ramped, like the colors.
 If the whole column is activated, this options functions like the equal interval classification (see the next option) only based on the first and last value of the class breaks, where the equal interval is based on the min and max value of the thematic attribute.
- Classify original data item. This option is used to classify the original data item. First, specify the number of requested classes in the #class's text box. Next, select one of the four types of classifications that are available:
 - Unique values (available for all data items with a number of unique occurrences that fits in the range of the domain unit): a class is added for each value that occurs in the data item. The number of classes is based on the number of unique occurrences. The maximum number of classes is dependent on the domain unit of the class unit.
 - Equal counts (available for all data items): the occurring data items are split up into classes with, as far as possible, an equal count of occurrences in each class. The class breaks are first set to the number of sorted data elements (excluding the no data values) divided by the number of requested classes. Each class break is checked to determine whether the next data element has the same value as the data element at the break. If this is the case, the class break is increased to the next data element, until a data element is found with a new value. If this data element is not found before the next class break, the last class break is removed and the number of classes is decreased by one class
 - Equal intervals (available for all items): the range of the data in a data item, or the specified range of a values unit, is split up in intervals of the same size. If no range is specified the default range for the value type of the unit is used.
 - *JenksFisher (natural breaks):* applies the <u>JenksFisher classification method</u> to minimize the variance within each class.
 - Logarithmic intervals (available for all items with a minimum value of zero): the range of the data in a data item or the specified range of a values unit is split up in intervals of the same size using a logarithmic distribution. If no range is specified the default range for the value type of the unit is used.
- **Copy Table** *class unit*: to copy the whole classification scheme.



PART III COMPOSERS

The feature of composing scripts for the GUI is now under consideration to be discontinued.

Introduction:

Composers are used to add or edit the configuration for a project. To use composers, the GeoDMS needs to run in the administrator mode. See paragraph 4.2.5, options menu, for how to run the GeoDMS in this mode.

Chapter 11: Insert Container

11.1 Containers

Containers in the GeoDMS are used to group subitems. They can be compared to the folders on a hard disk. A container is not a data item but can have an expression, if the container represents a case. The expression for a case consists of the calculation scheme with the set of selected parameter values. The Insert Container dialogue is mainly used for containers without expressions.

Select the tree item in which the container needs to be added as a subitem. Activate the main or pop-up menu option Insert Container (or the Ctrl-R keyboard combination). The Insert Container dialogue is presented:

S Insert Container			×
Name:			
Label:			
	Greate	Close	Help

11.2 Insert Container dialogue

Figure 11.1 Insert Container dialogue

In this dialogue the following properties of a new container can be specified:

Name (obligatory): the name of the container as shown in the Treeview. The following rules apply to a tree item name:

- only letters, numbers and underscores are allowed characters



- the first character may not be an underscore or a number

Label (optional): the label of the container that is presented in the primary data viewers and the property Detail Pages.

Description (optional): a more extensive description of the container, shown e.g. as a tooltip or in the property Detail Pages.

If the name of the container is specified, the Create button property becomes enabled. Click the button to add the container. The container is added with a \bigcirc icon, as it has no subitems yet. If subitems are added (and the Treeview is updated) the container will be presented with a \bigcirc icon (if the container has no data items as subitems) or with a \bigcirc icon.

Chapter 12: Insert Data Item

This functionality is in maintenance.



Chapter 13: Insert Entity/Unit

13.1 Values and domain units

All data items in the Geo DMS are defined by a name, a domain and a values unit. The domain unit determines to which collection a data item refers, e.g. municipalities in the Netherlands. Conceptually the domain unit is also called an entity, in database terms often implemented as a table. The domain unit determines if a data item can be geo-referenced and presented in a map view. Furthermore, it is an important consistency check in modelling, as for most operators it is not sensible to combine data items of multiple domains (e.g. it is not sensible to sum a data item NrInwoners per municipality with another NrInwoners data item per country). The Geo DMS checks this kind of inconstancies when an expression is made or edited.

A values unit describes how to interpret the values in terms of their value type (e.g. uint8, float32 or string) and their metric unit (the scientifically known unit, e.g. meter, second, 100 * kilogram etc.). Both the value type and the metric unit are important in modelling with data items. Data items with a values unit of a different value type can often not be combined in expressions unless the items are explicitly changed to another value type. The reason is that the result of an expression in which, for example, integers and floating point value units are combined is not defined in terms of their value type (for a complete list of the value types see the modeler's guide or the website: www.objectvision.nl/GeoDMS). For the metric unit, it depends on the operator if values units of different metric units can be combined in an expression. The sum of a data item with a metric unit of meters and another data item with a metric unit of seconds is not sensible. But the division of these items can be sensible, resulting in a data item that indicates the speed with a metric unit of a meter per second. The value type and the metric unit are also checked when an expression is inserted or edited.

13.2 Insert Entity/Unit dialogue

With the Insert Entity/Unit dialogue, new units can be added to the configuration. The unit is added as a subitem of the selected tree item from which the Insert Entity/Unit dialogue was activated. It is advisable to select the unit's container first and activate the dialogue with this tree item selected (unless a unit at another location in the tree is requested). The dialogue can be opened with the main or pop-up menu option: Insert Entity/Unit or with the Ctrl E keyboard combination. The following dialogue is presented:

~

T		F	- 14 A	/I I.	1.1
i in	sent	En	τιτν.	(\mathbf{U})	πιτ

)biect Vision

Select the unit type:		
Domain	A unit describing a numeric data item that indicates a quantitative characteristic, e.g. distance in meters	
○ <u>T</u> able unit	or output in Euro's.	
○ <u>G</u> rid unit		
/alues		
• Quantity unit		
C <u>P</u> oint unit		
C <u>S</u> hape unit		
C <u>C</u> ode unit		
C String unit		
C <u>B</u> oolean unit		
C Eocal point matrix		

Figure 13.1: Selection of the unit type in Insert Entity/Unit dialogue

With this dialogue, two types of domain units and seven types of values units can be configured. If a unit type is chosen a short description of the unit type is presented in blue text color at the right side of the dialogue. Click the Next button to configure the requested unit type.

For each unit type the following three properties can be configured:

Name (obligatory): the name of the unit as shown in the Treeview. The following rules apply to a tree item name:

- only letters, numbers and underscores are allowed characters
- the first character may not be an underscore or number -

Label (optional): the label of the unit that is presented in the primary data viewers, e.g. in the legend of the map view and in the Properties Detail Pages. In labels, all characters are allowed.

Description (optional) a more extensive description of the unit, (e.g. as a tooltip or in the Property Detail Pages). In descriptions, all characters are allowed.



13.3 Table unit

A Table unit is used to configure an entity with one-dimensional data items. In database terms this is often implemented in a table, resulting in the name table unit. The following dialogue is presented for this unit type:

Insert Entity/Unit	×
Table unit	
Name:	
Label:	
Description:	
Base unit	C <u>U</u> nique
Type: Count:	Sou <u>r</u> ce TU:
O <u>S</u> ubset	Filter:
Source TU:	Create countitem
<u>F</u> ilter:	C Union
○ Co <u>m</u> bine	Target VU:
A <u>v</u> ailable Selected	Available Selected
	< <u>B</u> ack Cancel OK Help

Figure 13.2: Insert Table unit dialogue

Within the GeoDMS GUI 7.163 a new table unit can be configured in five different ways:

- **Base unit**: A new table unit is requested that cannot be derived from other domain units. Activate the Base unit option, select a value type (uint32, uint16 or unit8 for table units) and a count (the number of elements of the table unit). Both elements need to be configured before the OK button becomes enabled and the unit can be added. Click the OK button to add the new domain unit.
- **Subset**: This option creates a new domain unit, based upon a selection of another domain unit (source table unit). Activate the Subset option, select the source table unit and a filter attribute by activating the button next to the text box. A dialogue is activated to select a tree item (see paragraph 13.3.1 for a description of this dialogue). The filter attributes presented are all Boolean attributes with the selected source table unit as domain unit. If no suitable filter



attribute is configured, a filter attribute needs to be created first with the Insert Data item dialogue (see chapter 12). Click the OK button to add the new domain unit.

- **Combine**: This option creates a new domain unit with the Cartesian product of a set of source table units (with a maximum of 8 source table units). This implies for each combination in the original table units a new entry is made in the new domain unit. Assume we have two table units, one with 600 municipalities and another with 10 years. The combined option results in a new domain unit with an entry for each municipality for each year, resulting in a new domain unit with 6.000 elements. To configure such a new domain unit, activate the combine option and select from the available units the source domain units that need to be combined with the arrow buttons:
 - Move all items from the available list to the selected list
 - Move the selected items from the available list to the selected list
 - Remove the selected items from the selected list
 - Kemove all items from the selected list

Click the OK button to add the new domain unit.

Unique: This option creates a new domain unit with the distinct, sorted values
of an attribute of a source table unit (e.g. municipality codes in a source domain
unit of neighborhoods). The unique operator can be compared to the distinct
operator in a SQL statement. To make a new table unit of these unique
occurrences, activate the unique option. Next, select the source table unit and

the filter attribute by activating the ... button. The filter attributes, presented are all attributes having the selected source table unit as domain unit. Usually, code attributes are relevant as a filter for this type of unit. The checkbox "create count item" can be optionally selected. This will result in a new attribute for the new domain unit with the number of occurrences of the filter attribute in the original domain. Click the OK button to add the new domain unit.

- **Union**: This option adds multiple domains together (e.g. domain units of cities in Netherlands, Belgium and Luxembourg are combined to a new domain unit, cities in the Benelux). To create a new domain unit with the union operator, attributes in the original domains need to be chosen that have the same values unit and can be united in the new domain. First, select a target values unit. For a selected values unit, the available attributes (with their domain units) are presented in the available list. Select the attributes that need to be united, with the arrow buttons (with a maximum of five):
 - >>> Move all items from the available list to the selected list
 - Move the selected items from the available list to the selected list
 - Remove the selected items from the selected list
 - Kemove all items from the selected list

Click the OK button to add the new domain unit.

13.3.1 TreeItem selection dialogue

In the Insert Entity/Unit dialogue at multiple places, a tree item needs to be selected. A generic dialogue is used in which the number and content of the columns can differ, based on the relevant information for the selection. The functionality of the dialogue



is similar. An example of the dialogue to select a source table unit for the subset option is described in Figure 13.3.

Select		
FullName	Nr. el	Projection
/Units/bblok_uint8 /Units/BeleidsIntensiteit /Units/Ls_Kwal_Klasse /Units/YearRange	255 6 6 200	
Filter: <no filter=""></no>		
[OK	Cancel

Figure 13.3: Tree item selection dialogue

In the dialogue, tree items can be sorted on each column by clicking the header of the column once (ascending) or twice (descending). Also, a filter can be applied by clicking the right mouse button on the header of the column and activating the pop-up menu option: Set filter. In a text box, a complete name or part of a name can be specified. The filter option is case insensitive. Activate the option again, leave the text box blank and click OK to remove the filter. This described dialogue is used for all locations where a tree item needs to be selected.

13.4 Grid unit

A Grid unit is used to configure an entity with two-dimensional data items, data items for which the domain is a grid or a matrix with an X and a Y coordinate. The following dialogue is used to configure a new grid unit:

Insert Entity/Unit							
Grid unit							
Name:							
_abel:							
Description:							
	×	.,					
Top-Left:	×	 y					
Bottom-Right:							
C Gridset unit							
<u>R</u> eference unit:		-					
	x	 у					
Scale factor:							
(0,0) <u>C</u> oordinate:							
Top-Left:							
Botto <u>m</u> -Right:							
			< Back	Can	cel	ок	Help

Figure 13.4: Insert Grid unit dialogue

A grid unit can be configured as a base unit or derived from another configured grid unit. Activate the base unit option to create a new grid domain that cannot be related to the existing grid unit. For a base unit the coordinate of the top left position and bottom right position need to be specified, to derive the range of the grid domain (e.g. the coordinate of the top left position of a rdc_500-meter grid unit is (0, 0) and the coordinate of the bottom right position is (650, 560)). Both coordinates need to be configured before the Ok button becomes enabled and the unit can be inserted.

If a grid unit is derived from another grid unit, activate the gridset unit option. Select the reference unit from which the new grid unit will be derived. The rdc_500 unit is e.g. a derived unit from rdc_meter. For derived units, additional to the top left and bottom right coordinate (as described for base units), a scale factor and a relation between the (0,0) coordinate of the new and the referred grid is necessary. The scale factor in both x and y directions specifies how 1 length unit in the referred grid needs to be interpreted in the new grid. The (0,0) coordinate specifies how the (0,0) position in the referred grid relates to the (0,0) position in the new grid. All these factors and coordinates need to be specified before the Ok button becomes enabled and the unit can be inserted.



13.5 Quantity unit

A quantity unit is used as values unit for numeric, non-geographic, data, describing a quantitative characteristic like distance in meters or land use in hectares. The following dialogue is used to configure a new quantity unit:

Insert Entity/Unit							<u> </u>
Quantity unit							
Name:							
_abel:							
Description:							
<u>B</u> ase unit							
<u>T</u> ype:	-	•					
C Derived unit							
E <u>x</u> pression							 \checkmark
) Metric							
			<	Back	Cancel	OK	Help

Figure 13.5: Insert Quantity unit dialogue

A quantity unit can be a new base unit (if the unit cannot be derived from another base unit) or a derived unit. If a quantity unit can be derived from another unit (for example square meter can be derived from an existing unit meter, with the expression meter * meter) it is advised to configure a derived unit, instead of a new base unit. If in the example square meter is defined as a derived unit with the expression meter * meter, the GeoDMS recognizes that square meters are a valid values unit for the multiplication of two data items with values units meters. If square meter was configured as a new base unit, this knowledge was not known to the Geo DMS. Configuring square meters as values unit of the result of a multiplication of two data items in meters.



If a new base unit is requested, activate the base unit option. Except for the name, label and description, only a value type needs to be selected. For quantity units, this is always float32 or float64. Click the OK button to add the configured unit.

If a new derived unit is requested, active the derived unit option. The check button

next to the expression box becomes enabled. An expression on how to derive the unit from existing units and constants need to be configured. For example, a new unit for cubic meters (m³) is requested. Type the expression Meter2 * Meter (or, Meter * Meter * Meter) in the Expression box. The full name of the tree items (Units/Meter) is not needed when the new unit is configured within the unit container. Activate the check button to check the syntax of the expression. If is it a valid expression, the check label on the button becomes green and the unit can be inserted. If it is not a valid expression, the label becomes red and an error is generated.

13.6 Point unit

A point unit is used as values unit for geographic data items that contain coordinates, e.g. in grids or in point shapes files. The following dialogue is used to configure a new point unit:

S Insert Entity/Ur	nit
Point unit	
<u>N</u> ame:	
Label:	
Description:	
<u>T</u> ype:	
T <u>o</u> p-Left:	x y
Botto <u>m</u> -Right:	
	< <u>B</u> ack Cancel OK Help

Figure 13.6: Insert Point unit dialogue



The value type of the point unit needs to be selected (for a complete list of the value types see the modeler's guide or the website: www.objectvision.nl/GeoDMS). The coordinate of the top left position and bottom right position can be specified, in order to derive the range of the point units, but unlike the grid domain for a point unit, this is optional. Activate the OK button to insert the unit.

13.7 Shape unit

A shape unit is used as values unit for geographic data items that contain sets of coordinates, e.g. in arc or polygon Shapefiles. The following dialogue is used to configure a new point shape unit:

Insert Entity/Ur	Init 📃	3
Shape unit		
<u>N</u> ame:		
Label:		
Description:		
<u>T</u> ype:	fpoint	
T <u>o</u> p-Left:	x y	
Botto <u>m</u> -Right:		
<u>F</u> ormat:		
	< <u>B</u> ack Cancel OK Help	

Figure 13.7: Insert Shape unit dialogue

The value type for the shape unit (fpoint or dpoint, see the modeler's guide or the website: www.objectvision.nl/GeoDMS, ipoint or spoint units cannot yet be configured with this dialogue) needs to be selected. The coordinate of the top left position and bottom right position can be specified, to derive the range of the shape unit (optional).



The format (polygon or arc) also need be specified. Activate the OK button to add the unit.

13.8 Code unit

A code unit is used as values unit for numeric data items that refer to codes/classes, e.g. municipality codes. A code unit has no expression and metric. The following dialogue is used to configure a new code unit:

S Insert Entity/U	Jnit
Code unit	
<u>N</u> ame:	
<u>L</u> abel:	
Description:	
<u>T</u> ype:	
<u>R</u> ange:	to
	< <u>B</u> ack Cancel OK Help

Figure 13.8: Insert Code unit dialogue

The value type for the code unit needs to be selected. For code units, the potential value types are all integer types and string units. The range of the unit can be configured (if known this is recommended and used by the Insert Classifications and Palette dialogue). Activate the OK button to insert the unit.

13.9 String unit

String units are used for data items that contain alphanumeric characters, e.g. municipality names. These data items are mainly used as labels. Except for the name,



label and description, no other information is required. Activate the OK button to insert the unit.

13.10 Boolean unit

Boolean units are used for data items that represent yes or no values. Except for the name, label and description, no other information is required. Activate the OK button to insert the unit.

13.11 Focal point matrix

The focal point matrix unit is a specific unit for potential calculations. The following dialogue is used to configure a new focal point matrix:

S Insert Entity/Unit	×
Focal point matrix (1/(d^2 + 2))	
Name:	
Label:	
Description:	
Distance:	
Subitems type:	
	< Back Cancel OK Help

Figure 13.9: Insert Focal point matrix dialogue

With this dialogue, a new spoint unit is created, with tree subitems for DistMatrX, AbsWeight and RelWeight. The specified distance (obligatory) determines the range of the new spoint unit. The value type of the subitems also needs to be specified in the combo box: Subitems type. Activate the OK button to insert the unit.



Chapter 14: Expression dialogue

14.1 Expressions

The model logic in the Geo DMS is implemented by configuring expressions for tree items. An expression is a calculation rule combining operators, data items and constants. In the default configuration, expressions are set to a number or tree items. Expressions can be edited or new expressions can be set with the Expression dialogue.

Select a tree item and activate the main or pop-up menu option Edit Definition (or the Ctrl-Alt-E keyboard combination). The Expression Dialog is presented. If the item has an expression configured, this is shown in the dialogue.

14.2 Expression dialogue

The following example shows the dialogue for the tree item: The following example shows the dialogue for the tree item: *RegioIndelingen/Gemeente/Corop_rel*



Figure 14.1 Expression dialogue

The expression dialogue consists of two parts. In the Expression box, the expression is shown. The Dependencies box at the bottom shows the dependencies (tree items with their full names) derived from the expression.

Tree items can be dragged into the Expression box from the Treeview and from the dependencies box. They can also be typed, but by using drag and drop typing errors in tree item names are expelled. Constants can be typed in the Expression box.

The contents of the expression dialogue can be copied to the Window clipboard by selecting the text (keep the left mouse button pressed, while moving over the text), clicking the right mouse button over the pop-up menu and choosing the copy option. The main menu option Edit Copy or the Control C keyboard combination cannot be used for this purpose, as they only apply to copying tree items.



14.3 Tools

If an expression dialogue is activated, the set of specific expression dialogue buttons is presented in the toolbar. The following buttons are available:



Clear expression: Button becomes enabled if an expression dialogue is not empty. Activate the button to remove the whole expression and clear the expression box.



Apply changes: Button becomes enabled if the configured expression is edited or a new expression is configured for the selected tree item. The apply changes tool first checks the syntax. If this is correct the new expression is stored in the tree item. If errors occur they are presented to the user.



Reset original expression: Button becomes enabled if the configured expression is edited or a new expression is configured for the selected tree item. The reset original expression resets the expression box to the original configured expression of the tree item selected when the dialogue was activated.



Syntax check: This button is used to check the syntax of the expression for following topics:

- Correct number of arguments for the operators
- Correct type of the arguments (e.g. a unit cannot be summed with a data item)
- Known tree items (e.g. a tree item with an incorrect name cannot be found)
- Correct domain and values units in calculations. Depending on the operators, combining items with a different domain and values units can cause errors.

The $\sqrt{}$ sign on the button can appear in four different colors:

Grey: no expression is configured, so the expression cannot be checked (disabled state).

Black: an expression is configured but not yet checked for a valid syntax.

Green: an expression is configured, checked and the syntax is correct.

Red: an expression is configured, checked but an error occurred in the syntax.



Update check: This button is used to check if the data item can really be updated. The syntax needs to be valid, but this does not guarantee the data item can be updated. (e.g. the file from which the primary data should be read is absent, or corrupt, or the data could cause divisions by zeroes, etc.). To be sure the data item can be updated, the update check can be activated, although this can take some time as it actually updates the tree item.



The **>** sign on the button can appear in four different colors:

Grey: no expression is configured, so the expression cannot be checked (disabled state).

Black: an expression is configured but not yet checked for an update.

Green: an expression is configured, checked and can be updated.

Red: an expression is configured, checked but an error did occur while updating


Chapter 15: Import/Export primary data

15.1 Introduction

Data items in the Geo DMS refer to primary data that can be stored in different formats. For some data items, with a limited amount of data, the primary data is stored in the configuration, like parameters and classifications. But for most data items the primary data is stored in external files. The Geo DMS reads the external files when the data is requested for viewing or calculating. In the configuration is specified which external data sources are used. The data does not explicitly have to be imported but is linked via the configuration. The external data formats that can be used within the GeoDMS are described <u>here</u>.

The configuration of data items linking to some external data formats can be performed with composers. Use the Insert External Datalink main or pop up menu option on a selected item that is requested as a parent for the configured of a new data source. The dialogues to configure new source data are described in paragraph 15.2

Most data items configured in the Geo DMS can be exported. This applies to both source data as well as model results. Based on the data item, the data can be exported to the following formats:

- Ascii grid
- Bitmap/Tiff
- Ascii attribute

Exporting data is an action, not resulting in a new (set of) tree item(s). The export option can be activated from the main File > Export primary data menu option or from the pop-up menu Export primary data, from which in a submenu a format needs to be selected. In paragraph 15.3 the different export formats and their dialogues are described.

15.2 Linking primary data

Data stored in an ASCII grid, shape, ODBC or DBF format can be configured with the GeoDMS GUI. Activate the Insert External Datalink menu option for the requested data format on the selected tree item that will be used as a parent for the configured ASCII grid. The following dialogues appear:



15.2.1 ASCII grid

Ninsert External	Datalink	
Ascii Grid		
<u>N</u> ame:		
<u>L</u> abel:		
Description:		
<u>A</u> scii grid:	e	
D <u>o</u> main unit:		
<u>V</u> alues unit:		
Configure at	ttribute of ascii grid	
Da <u>t</u> aitem:		

Figure 15.1: Insert External Datalink, ASCII grid dialogue

In this dialogue the following options can be configured:

Name (obligatory): the name of the container to which the ASCII grid file is configured, with subitems for the data in the grid (Griddata) and four parameters describing the ASCII grid (xllcorner, yllcorner, cell size and NODATA_val). The following rules apply to a tree item name:

- only letters, numbers and underscores are allowed characters
- the first character may not be an underscore or number -

It is advised to first select an ASCII grid file with the 🖻 button, next to the ASCII grid textbox. If an ASCII grid file is selected, the name of the tree item default receives the name of the ASCII grid without the file extension.

Label (optional): the label of the container that is presented in the Detail Pages. In labels, all characters are allowed.

Description (optional): a more extensive description of the container, (e.g. as a tooltip or in the Property Detail Pages). In descriptions, all characters are allowed.

ASCII grid (obligatory): the selected ASCII grid file, use the 🗎 button to activate a Windows file dialogue for the selection of an ASCII grid file. It is advised to start the dialogue with this selection, as the tree item name is derived from and the options for



the domain unit are depending on the selected ASCII grid file. The full path name is shown for a selected ASCII grid file.

Domain unit (obligatory): the grid domain unit, used as domain unit for the new

ASCII grid. First, an ASCII grid file needs to be selected. The selection button becomes enabled and can be activated to select a grid domain unit that fits the selected ASCII grid file. A grid domain unit fits if its number of rows and columns (specified by the range) equals the specified number of rows and columns in the ASCII grid. The dialogue used to select a domain unit is described in paragraph 13.3.1. If no suitable domain unit is found, a new domain unit (grid unit for ASCII grids) can be configured from the selection dialogue with the New button (See chapter 15 for how to configure a new grid unit).

Values unit (obligatory): the values in the ASCII grid need to be defined in terms of their values unit. For this reason, select a values unit with the selection/button. The dialogue used to select a values unit is described in paragraph 13.3.1. All numeric non-geographic values units, configured in the unit containers (as specified in the config.ini), are shown and can be selected.

Configure attribute of ASCII grid (optional): If an ASCII grid is fully configured, this option becomes enabled. In case a base grid is available, a selection can be made for the relevant values in an ASCII grid. This selection of values can be configured as an attribute, by activating the configure attribute of ASCII grid option. Activating the option enables the selection/button next to the Data item textbox. A base grid data item needs to be selected. With the extra option, an additional attribute is configured. This attribute has the same values unit as the grid data and the same domain unit as the base grid and contains the values from the relevant ASCII grid according to the values in the base grid.

By activating the OK button, the ASCII grid configuration is completed.



15.2.2 dBase (versions III, IV or V):

S Insert External [Datalink					X
dBase file						
Name:						-
Label:						-
Description:						-
dPace files						
u <u>B</u> ase file:	I					
Domain unit:			1 4			
<u>A</u> vailable attribu	tes:	<u>C</u> onfigur	ed attributes:	-	[_
Name	Туре	e Name		Туре	Values unit	- 1
		>				
		<				
۰ III	•	•	1	I		F
				<u>O</u> k	Cance	

Figure 15.2: Insert External Datalink, dBase dialog

With this dialogue the following options can be configured:

Name (obligatory): the name of the container to which the dBase file is configured, with subitems for the configured attributes. The following rules apply to a tree item name:

- only letters, numbers and underscores are allowed characters
- the first character may not be an underscore or number

It is advised to first select a dBase file with the button, next to the dBase textbox. If a dBase file is selected, the name of the tree item default receives the name of the dBase file without the file extension.

Label (optional): the label of the container that is presented in the Detail Pages. In labels, all characters are allowed.

Description (optional) a more extensive description of the container, e.g. as a tooltip or in the Property Detail Pages). In descriptions, all characters are allowed.



dBase file (obligatory): the selected dBase file, use the button to open a Windows file dialogue for the select a dBase file. *It is advised to start this dialogue with this selection, as the tree item name is derived from and the options for the domain units are depending on the selected dBase file.* The full path name is shown for a selected dBase file.

Domain unit (obligatory): the domain unit (table unit) for the dBase file (a dBase file always contains one table). First, a dBase file needs to be selected. The selection

button becomes enabled and can be activated to select a domain unit that fits the selected dBase file. A domain unit fits if its number of elements equals the number of records in the dBase file. The dialogue used to select a domain unit is described in paragraph 13.3.1. If no suitable domain unit is found, a new domain unit (table unit for dBase files) can be configured from the selection dialogue with the New button (See chapter 15 for how to configure a new table unit).

Data in a dBase file is stored in one or multiple attributes. If a dBase file is selected, all attributes of this file (except for the date and memo attributes) are shown in the

Available attributes box (including their value type). With the button, a selected attribute can be configured. The selection dialogue to select a values unit (this dialogue is described in paragraph 13.3.1) is activated. For each attribute to be configured a values unit must be selected. All non-geographic values units, configured in the unit containers (as specified in the config.ini), are shown and can be selected. After selecting a values unit, the attribute is added to the box of **Configured attributes**. If a wrong attribute is configured, or an attribute is configured with an incorrect values

unit, it can be removed from the list of configured attributes with the \leq button.

In the list of configured attributes can be specified if an attribute can be used as primary key. For dBase files sec, this is not used in the configuration. If the dBase file is part of a Shapefile configuration, it is needed to specify the primary key in the accompanying dBase file (see 15.2.4 Shape file configuration). The property if an attribute can be used as primary key for the table can be activated with a pop-up menu (right mouse click) and the option: Set as key.

By activating the OK button, the dBase configuration is completed.

15.2.3 ODBC source This functionality is in maintenance.

15.2.4 Shapefile This functionality is in maintenance.

15.3 Exporting primary data

Source data and model results can be exported to three different formats if the conditions that apply to the data formats are met.

15.3.1 ASCII grid

Grid data can be exported to an ASCII grid interchange format. Activate e.g. the main or pop up menu option Export Primary Data > ASCII grid for the container: *Referentie/Top100/GridData*. The following dialogue appears:



S Export Ascii Grid	_		×			
Container: /Referentie/Top100/GridData						
GridDomain	ata only	(unchec	k)			
Storage location: D:/LocalData/cursus/Results/stam/GridData.asc						
Show 1 exports Ok Cance		Help				

Figure 15.6: Export ASCII grid dialogue

The Grid domain indicates the domain unit(s) for the selected grid items. The 89 grid subitems of this container will be exported if the Ok button is selected. The following options are available:

The **Export also source data (check) or calculated data only (uncheck)** option is only available if the container would also contain source data, this is in this example not the case. If a container would also contain source data, this option can be used to indicate if these source items need to be exported as well (the option need to be checked).

The **Storage location** specifies the path to which the files will be exported. By default, the data items will be exported to a subdirectory of the results directory of the active configuration, named according to the container name, with as filename the name of the tree item and the extension .asc. A new directory and or file name can be chosen

with the button next to the Storage location textbox, which activates a Windows file dialogue.

The button Show 1 exports shows the list of data items that will be exported. This option can only be used to view the list of items, not to make selections.

15.3.2 Bitmap/Tiff

In the GeoDMS, Tiff and bitmaps of 255 colors are supported as export formats. This means a data item must be classified into a maximum of 255 classes, and for each class, a color value is written in the bitmap.



To export data to tiff or bitmap, three items must be configured:

- the storage location, path and file name of the result file
- a classification (unless the data item is a classified data item of values type (u)int8)
- a palette (with the color values for each class in the classification)

Classifications and palettes can be configured for a data item or for the values unit of the data item. Activate e.g. the pop up menu option Export Primary Data > Bitmap for the tree item: *Referentie/Top100/GridData*. The following dialogue appears:

😌 Export Bitma	р	-		×
<u>Storage location</u> D:/LocalData/	on: cursus/Results/stam/GridData.tif			
<u>R</u> elate to:	<don't basegrid="" use=""></don't>			•
Classification:	<don't classification="" use=""></don't>			•
<u>P</u> alette:	/Referentie/Top100/PaletteData			•
	<u>O</u> k <u>C</u> ance	el	Help	

Figure 15.7: Export Bitmap dialogue

The **Storage location** specifies the name of the file that will be created. By default, the data item will be exported to the results directory of the active configuration, with as filename the name of the tree item and the extension .tif. Change the extension to .bmp to export to a bitmap file. A new directory and or file name can be chosen with the button next to the textbox, which activates a Windows file dialogue. Together with the bitmap file, a bitmap/tiff world file is exported (with the extension tfw/bmpw), containing the coordinate information. This file is used e.g. by ArcView or ArcExplorer to `map' the bitmap in a used coordinate system.

In the **Relate to** combo box a base grid can be selected, if available

The **Classification** combo box presents the classifications configured for the data item or for the values unit of the data item. The default classification is selected, but another classification can be chosen with the combo box. If a data item is already classified, the text doesn't use classification appears. A classification is not necessary but, if available, still can be chosen.

The **Palette** combo box presents the available palettes for the selected classification. Often only one palette is available, but it is possible to configure multiple palettes for a classification (in the current version this is only possible with a text editor in the configuration files, not with the user interface of the application).



15.3.3 ASCII attribute

With the menu option Export Primary Data > ASCII attribute the content of a data item is written as an array to a plain text file (ASCII format). Activating the main or pop-up menu option activate a Windows file dialogue, with:

- By default, the results directory as location

- By default, the name of the tree item with the extension .txt as file name

ASCII attribute files can be made for almost all data items, except for geographic data formats (points, arcs and polygons).